Package: glpkAPI (via r-universe)

November 13, 2026

Type Package

Title R Interface to C API of GLPK

Version 1.3.4.9002

Depends R (>= 2.6.0)

Imports methods

Description R Interface to C API of GLPK, depends on GLPK Version >= 4.42. Compatibility updates by Renova.

SystemRequirements GLPK (>= 4.42)

License GPL-3 | file LICENSE

LazyLoad yes

Collate generics.R glpk_ptrClass.R glpk.R glpkAPI.R zzz.R

NeedsCompilation yes

Author Mihail Anton [cre], Mayo Roettger [ctb], Gabriel Gelius-Dietrich [aut], Louis Luangkesorn [ctb]

Maintainer Mihail Anton <mihail.anton@chalmers.se>

Config/pak/sysreqs libglpk-dev

Repository https://renova-r.r-universe.dev

Date/Publication 2026-11-13 19:48:30 UTC

RemoteUrl https://github.com/renova-r/glpkAPI

RemoteRef renova-1.3.4.9002

RemoteSha b32df84954618bbf0fa397dd0e5a6d6e4bbd8e87

Contents

glpkAPI-package 5
addColsGLPK 6
addRowsGLPK 7
advBasisGLPK 8
bfExistsGLPK 9
bfUpdatedGLPK 10

checkDupGLPK . . . 11
copyProbGLPK . . . 12
cpxBasisGLPK . . . 13
createIndexGLPK . . . 13
delColsGLPK . . . 14
deleteIndexGLPK . . . 15
delProbGLPK . . . 16
delRowsGLPK . . . 16
eraseProbGLPK . . . 17
factorizeGLPK . . . 18
findColGLPK . . . 19
findRowGLPK . . . 20
getBfcpGLPK . . . 21
getBheadGLPK . . . 22
getCbindGLPK . . . 23
getColDualGLPK . . . 24
getColDualIptGLPK . . . 25
getColKindGLPK . . . 26
getColLowBndGLPK . . . 27
getColNameGLPK . . . 28
getColPrimGLPK . . . 29
getColPrimIptGLPK . . . 30
getColsDualGLPK . . . 31
getColsDualIptGLPK . . . 31
getColsKindGLPK . . . 32
getColsLowBndsGLPK . . . 33
getColsPrimGLPK . . . 34
getColsPrimIptGLPK . . . 34
getColsStatGLPK . . . 35
getColStatGLPK . . . 36
getColsUppBndsGLPK . . . 37
getColTypeGLPK . . . 38
getColUppBndGLPK . . . 39
getDualStatGLPK . . . 40
getInteriorParmGLPK . . . 41
getMatColGLPK . . . 42
getMatRowGLPK . . . 43
getMIPParmGLPK . . . 44
getNumBinGLPK . . . 45
getNumColsGLPK . . . 45
getNumIntGLPK . . . 46
getNumNnzGLPK . . . 47
getNumRowsGLPK . . . 48
getObjCoefGLPK . . . 48
getObjCoefsGLPK . . . 49
getObjDirGLPK . . . 50
getObjNameGLPK . . . 51
getObjValGLPK . . . 52

getObjValIptGLPK 52
getPrimStatGLPK 53
getProbNameGLPK 54
getRbindGLPK 55
getRiiGLPK 56
getRowDualGLPK 57
getRowDualIptGLPK 58
getRowLowBndGLPK 59
getRowNameGLPK 60
getRowPrimGLPK 61
getRowPrimIptGLPK 62
getRowsDualGLPK 63
getRowsDualIptGLPK 63
getRowsLowBndsGLPK 64
getRowsPrimGLPK 65
getRowsPrimIptGLPK 66
getRowsStatGLPK 66
getRowStatGLPK 67
getRowsTypesGLPK 68
getRowsUppBndsGLPK 69
getRowTypeGLPK 70
getRowUppBndGLPK 71
getSimplexParmGLPK 72
getSjjGLPK 73
getSolStatGLPK 74
getSolStatIptGLPK 75
getUnbndRayGLPK 76
glpkConstants 77
glpkPtr-class 83
initProbGLPK 84
loadMatrixGLPK 85
mipColsValGLPK 86
mipColValGLPK 87
mipObjValGLPK 88
mipRowsValGLPK 88
mipRowValGLPK 89
mipStatusGLPK 90
mplAllocWkspGLPK 91
mplBuildProbGLPK 92
mplFreeWkspGLPK 93
mplGenerateGLPK 94
mplPostsolveGLPK 95
mplReadDataGLPK 96
mplReadModelGLPK 97
printIptGLPK 98
printMIPGLPK 99
printRangesGLPK 100
printSolGLPK 101

readIptGLPK . . . 102
readLPGLPK . . . 103
readMIPGLPK . . . 104
readMPSGLPK . . . 105
readProbGLPK . . . 106
readSolGLPK . . . 107
return_codeGLPK . . . 108
scaleProbGLPK . . . 108
setBfcpGLPK . . . 109
setColBndGLPK . . . 110
setColKindGLPK . . . 111
setColNameGLPK . . . 112
setColsBndsGLPK . . . 113
setColsBndsObjCoefsGLPK . . . 114
setColsKindGLPK . . . 115
setColsNamesGLPK . . . 116
setColStatGLPK . . . 117
setDefaultIptParmGLPK . . . 118
setDefaultMIPParmGLPK . . . 118
setDefaultSmpParmGLPK . . . 119
setInteriorParmGLPK . . . 120
setMatColGLPK . . . 121
setMatRowGLPK . . . 122
setMIPParmGLPK . . . 123
setObjCoefGLPK . . . 124
setObjCoefsGLPK . . . 125
setObjDirGLPK . . . 126
setObjNameGLPK . . . 127
setProbNameGLPK . . . 128
setRhsZeroGLPK . . . 129
setRiiGLPK . . . 129
setRowBndGLPK . . . 130
setRowNameGLPK . . . 131
setRowsBndsGLPK . . . 132
setRowsNamesGLPK . . . 133
setRowStatGLPK . . . 134
setSimplexParmGLPK . . . 135
setSjjGLPK . . . 136
solveInteriorGLPK . . . 137
solveMIPGLPK . . . 138
solveSimplexExactGLPK . . . 139
solveSimplexGLPK . . . 140
sortMatrixGLPK . . . 141
status_codeGLPK . . . 141
stdBasisGLPK . . . 142
termOutGLPK . . . 143
unscaleProbGLPK . . . 144
versionGLPK . . . 144

warmUpGLPK 145
writeIptGLPK 146
writeLPGLPK 147
writeMIPGLPK 148
writeMPSGLPK 149
writeProbGLPK 150
writeSolGLPK 151

Index **152**

`glpkAPI-package` *R Interface to C API of GLPK*

Description

A low level interface to the GNU Linear Programming Kit (GLPK).

Details

The package `glpkAPI` provides access to the callable library of the GNU Linear Programming Kit from within R.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

Examples

```
# load package
library(glpkAPI)

# preparing the model
lp <- initProbGLPK()

# model data
nrows  <- 5
ncols  <- 8

# constraint matrix
ne <- 14
ia <- c(1, 5, 1, 2, 2, 3, 1, 4, 1, 5, 3, 4, 1, 5)
ja <- c(1, 1, 2, 2, 3, 3, 4, 4, 5, 5, 6, 7, 8, 8)
ar <- c(3.0, 5.6, 1.0, 2.0, 1.1, 1.0, -2.0, 2.8,
```

```
        -1.0, 1.0, 1.0, -1.2, -1.0, 1.9)

# objective function
obj <- c(1, 0, 0, 0, 2, 0, 0, -1)

# upper and lower bounds of the rows
rlower <- c(2.5, -1000, 4, 1.8, 3)
rupper <- c(1000, 2.1, 4, 5, 15)

# upper and lower bounds of the columns
clower <- c(2.5, 0, 0, 0, 0.5, 0, 0, 0)
cupper <- c(1000, 4.1, 1, 1, 4, 1000, 1000, 4.3)

# direction of optimization
setObjDirGLPK(lp, GLP_MIN)

# add rows and columns
addRowsGLPK(lp, nrows)
addColsGLPK(lp, ncols)

setColsBndsObjCoefsGLPK(lp, c(1:ncols), clower, cupper, obj)
setRowsBndsGLPK(lp, c(1:nrows), rlower, rupper)

# load constraint matrix
loadMatrixGLPK(lp, ne, ia, ja, ar)

# solve lp problem
solveSimplexGLPK(lp)

# retrieve the results
getSolStatGLPK(lp)
getObjValGLPK(lp)
getColsPrimGLPK(lp)

# remove problem object
delProbGLPK(lp)
```

`addColsGLPK` *Add Columns to a GLPK Problem Object*

Description

Low level interface function to the GLPK function `glp_add_cols`. Consult the GLPK documentation for more detailed information.

Usage

```
addColsGLPK(lp, ncols)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
ncols	The number of columns to add.

Details

Interface to the C function addCols which calls the GLPK function glp_add_cols.

Value

The ordinal number of the first new column added to the problem object is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html

---

addRowsGLPK *Add Rows to a GLPK Problem Object*

Description

Low level interface function to the GLPK function glp_add_rows. Consult the GLPK documentation for more detailed information.

Usage

```
addRowsGLPK(lp, nrows)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
nrows	The number of rows to add.

Details

Interface to the C function addRows which calls the GLPK function glp_add_rows.

Value

The ordinal number of the first new row added to the problem object is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html

---

`advBasisGLPK` *Contruct Advanced Initial LP Basis*

Description

Low level interface function to the GLPK function `glp_adv_basis`. Consult the GLPK documentation for more detailed information.

Usage

```
advBasisGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `advBasis` which calls the GLPK function `glp_adv_basis`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html

bfExistsGLPK *Check if the basis factorization exists*

Description

Low level interface function to the GLPK function `glp_bf_exists`. Consult the GLPK documentation for more detailed information.

Usage

```
bfExistsGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `bfExists` which calls the GLPK function `glp_bf_exists`.

Value

Returns non-zero if the basis factorization for the specified problem object exists. Otherwise the routine returns zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`bfUpdatedGLPK` *Check if the basis factorization has been updated*

Description

Low level interface function to the GLPK function `glp_bf_updated`. Consult the GLPK documentation for more detailed information.

Usage

```
bfUpdatedGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `bfUpdated` which calls the GLPK function `glp_bf_updated`.

Value

Returns non-zero if the basis factorization has been updated at least once. Otherwise the routine returns zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

checkDupGLPK *Check for Duplicate Elements in Sparse Matrix*

Description

Low level interface function to the GLPK function `glp_check_dup`. Consult the GLPK documentation for more detailed information.

Usage

```
checkDupGLPK(m, n, ne, ia, ja)
```

Arguments

`m`	Number of rows in the matrix.
`n`	Number of columns in the matrix.
`ne`	Number of non-zero elements in the matrix.
`ia`	Row indices of the non-zero elements.
`ja`	Column indices of the non-zero elements.

Details

Interface to the C function `checkDup` which calls the GLPK function `glp_check_dup`.

Value

Returns one of the following values:

`0`	No duplikate elements.
`-k`	Indices `ia[k]` or `ja[k]` are out of range.
`+k`	Element `(ia[k], ja[k])` is duplicate.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html

copyProbGLPK *Copy problem object content*

Description

Low level interface function to the GLPK function `glp_copy_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
copyProbGLPK(lp, clp, name = GLP_OFF)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`clp`	A pointer to a GLPK problem object (destination).
`name`	If set to `GLP_ON`, the routine copies all symbolic names; otherwise (`GLP_OFF`) not.

Details

Interface to the C function `copyProb` which calls the GLPK function `glp_copy_prob`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'enable/disable flag'.

cpxBasisGLPK *Construct Bixby's initial LP basis*

Description

Low level interface function to the GLPK function `glp_cpx_basis`. Consult the GLPK documentation for more detailed information.

Usage

```
cpxBasisGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `cpxBasis` which calls the GLPK function `glp_cpx_basis`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

createIndexGLPK *Create the Name Index*

Description

Low level interface function to the GLPK function `glp_create_index`. Consult the GLPK documentation for more detailed information.

Usage

```
createIndexGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function createIndex which calls the GLPK function glp_create_index.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

delColsGLPK *Delete Columns from Problem Object*

Description

Low level interface function to the GLPK function glp_del_cols. Consult the GLPK documentation for more detailed information.

Usage

```
delColsGLPK(lp, ncols, j)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
ncols	Number of columns to delete.
j	Ordinal numbers of columns to delete.

Details

Interface to the C function delCols which calls the GLPK function glp_del_cols.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

deleteIndexGLPK *Delete the Name Index*

Description

Low level interface function to the GLPK function `glp_delete_index`. Consult the GLPK documentation for more detailed information.

Usage

```
deleteIndexGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `deleteIndex` which calls the GLPK function `glp_delete_index`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

delProbGLPK *Delete Problem Object*

Description

Low level interface function to the GLPK function `glp_delete_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
delProbGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `delProb` which calls the GLPK function `glp_delete_prob`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

delRowsGLPK *Delete Rows from Problem Object*

Description

Low level interface function to the GLPK function `glp_del_rows`. Consult the GLPK documentation for more detailed information.

Usage

```
delRowsGLPK(lp, nrows, i)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
nrows	Number of rows to delete.
i	Ordinal numbers of rows to delete.

Details

Interface to the C function delRows which calls the GLPK function glp_del_rows.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

eraseProbGLPK *Erase problem object content*

Description

Low level interface function to the GLPK function glp_erase_prob. Consult the GLPK documentation for more detailed information.

Usage

```
eraseProbGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function eraseProb which calls the GLPK function glp_erase_prob.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`factorizeGLPK` *Compute the basis factorization*

Description

Low level interface function to the GLPK function `glp_factorize`. Consult the GLPK documentation for more detailed information.

Usage

```
factorizeGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `factorize` which calls the GLPK function `glp_factorize`.

Value

Returns zero if the basis factorization has been successfully computed. Otherwise the routine returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'return codes'.

`findColGLPK` *Find Column by its Name*

Description

Low level interface function to the GLPK function `glp_find_col`. Consult the GLPK documentation for more detailed information.

Usage

```
findColGLPK(lp, cname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`cname`	A column name.

Details

Interface to the C function `findCol` which calls the GLPK function `glp_find_column`.

Value

Returns the ordinal number of a column, which is assigned the specified cname.

Note

Before calling `findColGLPK` for the first time on a problem object `lp`, an index has to created via a call to `createIndexGLPK`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

findRowGLPK *Find Row by its Name*

Description

Low level interface function to the GLPK function `glp_find_row`. Consult the GLPK documentation for more detailed information.

Usage

```
findRowGLPK(lp, rname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`rname`	A row name.

Details

Interface to the C function `findRow` which calls the GLPK function `glp_find_row`.

Value

Returns the ordinal number of a row, which is assigned the specified rname.

Note

Before calling `findRowGLPK` for the first time on a problem object `lp`, an index has to created via a call to `createIndexGLPK`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getBfcpGLPK *Retrieve Basis Factorization Control parameters*

Description

Returns the names and values of members in the structure glp_bfcp. Consult the GLPK documentation for more detailed information.

Usage

```
getBfcpGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getBfcp.

Value

The function returns a list.

integer	The names and corresponding values of all integer control parameters in glp_bfcp.
double	The names and corresponding values of all double control parameters in glp_bfcp.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'Control Parameters'.

getBheadGLPK *Retrieve Basis Header Information*

Description

Low level interface function to the GLPK function `glp_get_bhead`. Consult the GLPK documentation for more detailed information.

Usage

```
getBheadGLPK(lp, k)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`k`	Index of the basic variable.

Details

Interface to the C function `getBhead` which calls the GLPK function `glp_get_bhead`.

Value

Index of the auxiliary/structural variable.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getCbindGLPK *Retrieve Column Index in the Basis Header*

Description

Low level interface function to the GLPK function `glp_get_col_bind`. Consult the GLPK documentation for more detailed information.

Usage

```
getCbindGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Structural variable `j`.

Details

Interface to the C function `getCbind` which calls the GLPK function `glp_get_col_bind`.

Value

Index of the basic variable.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColDualGLPK` *Retrieve Column Dual Value*

Description

Low level interface function to the GLPK function `glp_get_col_dual`. Consult the GLPK documentation for more detailed information.

Usage

```
getColDualGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.

Details

Interface to the C function `getColDual` which calls the GLPK function `glp_get_col_dual`.

Value

Column dual value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColDualIptGLPK` *Retrieve Column Dual Value*

Description

Low level interface function to the GLPK function `glp_ipt_col_dual`. Consult the GLPK documentation for more detailed information.

Usage

```
getColDualIptGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.

Details

Interface to the C function `getColDualIpt` which calls the GLPK function `glp_ipt_col_dual`.

Value

Column dual value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColKindGLPK` *Retrieve Column Kind*

Description

Low level interface function to the GLPK function `glp_get_col_kind`. Consult the GLPK documentation for more detailed information.

Usage

```
getColKindGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.

Details

Interface to the C function `getColKind` which calls the GLPK function `glp_get_col_kind`.

Value

Column Kind

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getColLowBndGLPK *Retrieve Column Lower Bound*

Description

Low level interface function to the GLPK function `glp_get_col_lb`. Consult the GLPK documentation for more detailed information.

Usage

```
getColLowBndGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColLowBnd` which calls the GLPK function `glp_get_col_lb`.

Value

The lower bound of the `j`-th column (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getColNameGLPK *Retrieve Column Name*

Description

Low level interface function to the GLPK function `glp_get_col_name`. Consult the GLPK documentation for more detailed information.

Usage

```
getColNameGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColName` which calls the GLPK function `glp_get_col_name`.

Value

The assigned name of the `j`-th column is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColPrimGLPK` *Retrieve Column Primal Value*

Description

Low level interface function to the GLPK function `glp_get_col_prim`. Consult the GLPK documentation for more detailed information.

Usage

```
getColPrimGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColPrim` which calls the GLPK function `glp_get_col_prim`.

Value

The primal value of the `j`-th column (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColPrimIptGLPK` *Retrieve Column Primal Value*

Description

Low level interface function to the GLPK function `glp_ipt_col_prim`. Consult the GLPK documentation for more detailed information.

Usage

```
getColPrimIptGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColPrimIpt` which calls the GLPK function `glp_ipt_col_prim`.

Value

The primal value of the `j`-th column (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getColsDualGLPK *Retrieve Column Dual Value of all Columns*

Description

This is an advanced version of getColDualGLPK.

Usage

```
getColsDualGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getColsDual which calls the GLPK function glp_get_col_dual.

Value

The column dual values of all columns (structural variables) are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getColsDualIptGLPK *Retrieve Column Dual Value of all Columns*

Description

This is an advanced version of getColDualIptGLPK.

Usage

```
getColsDualIptGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getColDualIpt which calls the GLPK function glp_ipt_col_dual.

Value

The column dual values of all columns are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getColsKindGLPK *Retrieve Column Kind*

Description

This is an advanced version of getColKindGLPK.

Usage

```
getColsKindGLPK(lp, j)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Vector of column numbers.

Details

Interface to the C function getColsKind which calls the GLPK function glp_get_col_ub.

Value

The column kinds of all specified columns (j) are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getColsLowBndsGLPK *Retrieve Lower Bounds of Specified Columns*

Description

This is an advanced version of `getColLowBndGLPK`. Here, `j` can be an integer vector.

Usage

```
getColsLowBndsGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Vector of column numbers.

Details

Interface to the C function `getColsLowBnds` which calls the GLPK function `glp_get_col_lb`.

Value

The lower bounds of all specified columns (`j`) (the corresponding structural variables) are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getColsPrimGLPK *Retrieve all Column Primal Values*

Description

This is an advanced version of getColPrimGLPK.

Usage

```
getColsPrimGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getColsPrim which calls the GLPK functions glp_get_col_prim and glp_get_num_cols.

Value

Returns all values of the stuctural variables as a numeric vector.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getColsPrimIptGLPK *Retrieve all Column Primal Values*

Description

This is an advanced version of getColPrimGLPK.

Usage

```
getColsPrimIptGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getColsPrimIpt which calls the GLPK functions glp_ipt_col_prim and glp_get_num_cols.

Value

Returns all values of the stuctural variables as a numeric vector.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getColsStatGLPK *Retrieve Column Status of all Columns*

Description

This is an advanced version of getColStatGLPK.

Usage

```
getColsStatGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getColsStat which calls the GLPK function glp_get_col_stat.

Value

The column status of all columns are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getColStatGLPK *Retrieve Column Status*

Description

Low level interface function to the GLPK function `glp_get_col_stat`. Consult the GLPK documentation for more detailed information.

Usage

```
getColStatGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.

Details

Interface to the C function `getColStat` which calls the GLPK function `glp_get_col_stat`.

Value

Column status

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

`getColsUppBndsGLPK` *Retrieve Upper Bounds of Specified Columns*

Description

This is an advanced version of `getColUppBndGLPK`. Here, `j` can be an integer vector.

Usage

```
getColsUppBndsGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Vector of column numbers.

Details

Interface to the C function `getColsUppBnds` which calls the GLPK function `glp_get_col_ub`.

Value

The upper bounds of all specified columns (`j`) (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getColTypeGLPK` *Retrieve Column Type*

Description

Low level interface function to the GLPK function `glp_get_col_type`. Consult the GLPK documentation for more detailed information.

Usage

```
getColTypeGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColType` which calls the GLPK function `glp_get_col_type`.

Value

The type of the `j`-th column (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

getColUppBndGLPK *Retrieve Column Upper Bound*

Description

Low level interface function to the GLPK function `glp_get_col_ub`. Consult the GLPK documentation for more detailed information.

Usage

```
getColUppBndGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getColUppBnd` which calls the GLPK function `glp_get_col_ub`.

Value

The upper bound of the `j`-th column (the corresponding structural variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getDualStatGLPK *Retrieve Status of Dual Basic Solution*

Description

Low level interface function to the GLPK function `glp_get_dual_stat`. Consult the GLPK documentation for more detailed information.

Usage

```
getDualStatGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getDualStat` which calls the GLPK function `glp_get_dual_stat`.

Value

Status of dual basic solution

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

`getInteriorParmGLPK` *Retrives the Control Parameters for the Interior-point Method.*

Description

Returns the names and values of members in the structure `glp_iptcp`. Consult the GLPK documentation for more detailed information.

Usage

```
getInteriorParmGLPK()
```

Details

Interface to the C function `getInteriorParm`.

Value

The function returns a list.

`integer`	The names and corresponding values of all integer control parameters in `glp_iptcp`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`, section 'Control Parameters'.

getMatColGLPK *Retrieves Column j of the Constraint Matrix.*

Description

Low level interface function to the GLPK function `glp_get_mat_col`. Consult the GLPK documentation for more detailed information.

Usage

```
getMatColGLPK(lp, j)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getMatCol` which calls the GLPK functions `glp_get_num_rows` and `glp_get_mat_col`.

Value

Returns NULL or a list containing the non zero elements of column j:

`nnz`	number of non zero elements in column j
`index`	row indices of the non zero elements in column j
`value`	numerical values of the non zero elements in column j

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getMatRowGLPK *Retrieves Row i of the Constraint Matrix.*

Description

Low level interface function to the GLPK function `glp_get_mat_row`. Consult the GLPK documentation for more detailed information.

Usage

```
getMatRowGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getMatRow` which calls the GLPK functions `glp_get_num_cols` and `glp_get_mat_row`.

Value

Returns NULL or a list containing the non zero elements of row i:

`nnz`	number of non zero elements in row i
`index`	column indices of the non zero elements in row i
`value`	numerical values of the non zero elements in row i

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getMIPParmGLPK` *Retrives the Control Parameters for MIP.*

Description

Returns the names and values of members in the structure `glp_iocp`. Consult the GLPK documentation for more detailed information.

Usage

```
getMIPParmGLPK()
```

Details

Interface to the C function `getMIPParm`.

Value

The function returns a list.

`integer`	The names and corresponding values of all integer control parameters in `glp_iocp`.
`double`	The names and corresponding values of all double control parameters in `glp_iocp`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`, section 'Control Parameters'.

getNumBinGLPK *Retrieve Number of Binary Columns*

Description

Low level interface function to the GLPK function `glp_get_num_bin`. Consult the GLPK documentation for more detailed information.

Usage

```
getNumBinGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getNumBin` which calls the GLPK function `glp_get_num_bin`.

Value

Number of binary columns.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getNumColsGLPK *Retrieve Number of Columns*

Description

Low level interface function to the GLPK function `glp_get_num_cols`. Consult the GLPK documentation for more detailed information.

Usage

```
getNumColsGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getNumCols which calls the GLPK function glp_get_num_cols.

Value

Returns the current number of columns in the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getNumIntGLPK *Retrieve Number of Integer Columns*

Description

Low level interface function to the GLPK function glp_get_num_int. Consult the GLPK documentation for more detailed information.

Usage

```
getNumIntGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getNumInt which calls the GLPK function glp_get_num_int.

Value

Number of integer columns.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getNumNnzGLPK *Retrieve the Number of Constraint Coefficients*

Description

Low level interface function to the GLPK function `glp_get_num_nz`. Consult the GLPK documentation for more detailed information.

Usage

```
getNumNnzGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getNumNnz` which calls the GLPK function `glp_get_num_nz`.

Value

Returns the number of non-zero elements in the constraint matrix of the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getNumRowsGLPK *Retrieve Number of Rows*

Description

Low level interface function to the GLPK function `glp_get_num_rows`. Consult the GLPK documentation for more detailed information.

Usage

```
getNumRowsGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getNumRows` which calls the GLPK function `glp_get_num_rows`.

Value

Returns the current number of rows in the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getObjCoefGLPK *Retrieve Objective Coefficient or Constant Term*

Description

Low level interface function to the GLPK function `glp_get_obj_coef`. Consult the GLPK documentation for more detailed information.

Usage

```
getObjCoefGLPK(lp, j)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Column number j.

Details

Interface to the C function getObjCoef which calls the GLPK function glp_get_obj_coef.

Value

The objective coefficient at the j-th column (the corresponding structural variable) is returned. If j is 0, the constant term "shift" of the objective function is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getObjCoefsGLPK *Retrieve Objective Coefficients at Specified Columns and/or Constant Term*

Description

This is an advanced version of getObjCoefGLPK. Here, j can be an integer vector.

Usage

```
getObjCoefsGLPK(lp, j)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Vector of column numbers.

Details

Interface to the C function getObjCoef which calls the GLPK function glp_get_obj_coef.

Value

The objective coefficient at all specified columns (`j`) (the corresponding structural variable) is returned. If `j` is `0`, the constant term "shift" of the objective function is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`getObjDirGLPK` *Retrieve Optimization Direction Flag*

Description

Low level interface function to the GLPK function `glp_get_obj_dir`. Consult the GLPK documentation for more detailed information.

Usage

```
getObjDirGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getObjDir` which calls the GLPK function `glp_get_obj_dir`.

Value

Returns the optimization direction flag.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'LP/MIP problem object'.

`getObjNameGLPK` *Retrieve Objective Function Name*

Description

Low level interface function to the GLPK function `glp_get_obj_name`. Consult the GLPK documentation for more detailed information.

Usage

```
getObjNameGLPK(lp)
```

Arguments

`lp`	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getObjName` which calls the GLPK function `glp_get_obj_name`.

Value

The assigned name of the objective function is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getObjValGLPK *Retrieve Objective Value*

Description

Low level interface function to the GLPK function `glp_get_obj_val`. Consult the GLPK documentation for more detailed information.

Usage

```
getObjValGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getObjVal` which calls the GLPK function `glp_get_obj_val`.

Value

Returns the current value of the objective function.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getObjValIptGLPK *Retrieve Objective Value*

Description

Low level interface function to the GLPK function `glp_ipt_obj_val`. Consult the GLPK documentation for more detailed information.

Usage

```
getObjValIptGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getObjValIpt which calls the GLPK function glp_ipt_obj_val.

Value

Returns the current value of the objective function.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getPrimStatGLPK *Retrieve Status of Primal Basic Solution*

Description

Low level interface function to the GLPK function glp_get_prim_stat. Consult the GLPK documentation for more detailed information.

Usage

```
getPrimStatGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getPrimStat which calls the GLPK function glp_get_prim_stat.

Value

Status of primal basic solution

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'LP/MIP problem object'.

---

getProbNameGLPK *Retrieve Problem Name*

Description

Low level interface function to the GLPK function glp_get_prob_name. Consult the GLPK documentation for more detailed information.

Usage

```
getProbNameGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getProbName which calls the GLPK function glp_get_prob_name.

Value

The assigned name of the problem is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getRbindGLPK *Retrieve Row Index in the Basis Header*

Description

Low level interface function to the GLPK function `glp_get_row_bind`. Consult the GLPK documentation for more detailed information.

Usage

```
getRbindGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Auxiliary variable `i`.

Details

Interface to the C function `getRbind` which calls the GLPK function `glp_get_row_bind`.

Value

Index of the basic variable.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getRiiGLPK *Retrieve row scale factor*

Description

Low level interface function to the GLPK function `glp_get_rii`. Consult the GLPK documentation for more detailed information.

Usage

```
getRiiGLPK(lp, i)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getRii` which calls the GLPK function `glp_get_rii`.

Value

Returns the current scale factor r_ii for row `i` of the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getRowDualGLPK` *Retrieve Row Dual Value*

Description

Low level interface function to the GLPK function `glp_get_row_dual`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowDualGLPK(lp, i)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number `i`.

Details

Interface to the C function `getRowDual` which calls the GLPK function `glp_get_row_dual`.

Value

Row dual value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getRowDualIptGLPK` *Retrieve Row Dual Value*

Description

Low level interface function to the GLPK function `glp_ipt_row_dual`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowDualIptGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number `i`.

Details

Interface to the C function `getRowDualIpt` which calls the GLPK function `glp_ipt_row_dual`.

Value

Row dual value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getRowLowBndGLPK` *Retrieve Row Lower Bound*

Description

Low level interface function to the GLPK function `glp_get_row_lb`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowLowBndGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getRowLowBnd` which calls the GLPK function `glp_get_row_lb`.

Value

The lower bound of the `i`-th row (the corresponding auxiliary variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getRowNameGLPK *Retrieve Row Name*

Description

Low level interface function to the GLPK function `glp_get_row_name`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowNameGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getRowName` which calls the GLPK function `glp_get_row_name`.

Value

The assigned name of the `i`-th row is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getRowPrimGLPK` *Retrieve Row Primal Value*

Description

Low level interface function to the GLPK function `glp_get_row_prim`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowPrimGLPK(lp, i)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number `i`.

Details

Interface to the C function `getRowPrim` which calls the GLPK function `glp_get_row_prim`.

Value

Row primal value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getRowPrimIptGLPK *Retrieve Row Primal Value*

Description

Low level interface function to the GLPK function `glp_ipt_row_prim`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowPrimIptGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number `i`.

Details

Interface to the C function `getRowPrimIpt` which calls the GLPK function `glp_ipt_row_prim`.

Value

Row primal value

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getRowsDualGLPK *Retrieve Row Dual Values of all Rows*

Description

This is an advanced version of getRowDualGLPK.

Usage

```
getRowsDualGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getRowsDual which calls the GLPK function glp_get_row_stat.

Value

The row dual values of all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getRowsDualIptGLPK *Retrieve Row Dual Value of all Rows*

Description

This is an advanced version of getRowDualIptGLPK.

Usage

```
getRowsDualIptGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getRowsDualIpt which calls the GLPK function glp_ipt_row_dual.

Value

The row dual values of all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getRowsLowBndsGLPK *Retrieve Lower Bounds of Specified Rows*

Description

This is an advanced version of getRowLowBndGLPK. Here, i can be an integer vector.

Usage

```
getRowsLowBndsGLPK(lp, i)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Vector of row numbers.

Details

Interface to the C function getRowsLowBnds which calls the GLPK function glp_get_row_lb.

Value

The lower bounds of all specified columns (i) (the corresponding auxiliary variables) are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

getRowsPrimGLPK *Retrieve Row Primal Value of all Rows*

Description

This is an advanced version of getRowPrimGLPK.

Usage

```
getRowsPrimGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getRowsPrim which calls the GLPK function glp_get_row_prim.

Value

The row primal values for all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getRowsPrimIptGLPK *Retrieve Row Primal Value of all Rows*

Description

This is an advanced version of getRowPrimIptGLPK.

Usage

```
getRowsPrimIptGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function getRowsPrimIpt which calls the GLPK function glp_ipt_row_prim.

Value

The row primal values of all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getRowsStatGLPK *Retrieve Row Status of all Rows*

Description

This is an advanced version of getRowStatGLPK.

Usage

```
getRowsStatGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getRowsStat` which calls the GLPK function `glp_get_row_stat`.

Value

The row status values of all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getRowStatGLPK` *Retrieve Row Status*

Description

Low level interface function to the GLPK function `glp_get_row_stat`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowStatGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number `i`.

Details

Interface to the C function `getRowStat` which calls the GLPK function `glp_get_row_stat`.

Value

Row status

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'LP/MIP problem object'.

---

getRowsTypesGLPK *Retrieve Types of Specified Constraints (Rows)*

Description

This is an advanced version of getRowTypeGLPK. Here, i can be an integer vector.

Usage

```
getRowsTypesGLPK(lp, i)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Vector of row numbers.

Details

Interface to the C function getRowsTypes which calls the GLPK function glp_get_row_type.

Value

A numeric vector of the same length as i giving the constraint type of the specified rows.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'type of auxiliary/structural variable'.

---

getRowsUppBndsGLPK *Retrieve Upper Bounds of Specified Rows*

Description

This is an advanced version of getRowUppBndGLPK. Here, i can be an integer vector.

Usage

```
getRowsUppBndsGLPK(lp, i)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Vector of row numbers.

Details

Interface to the C function getRowsUppBnds which calls the GLPK function glp_get_row_ub.

Value

The upper bounds of all specified columns (i) (the corresponding auxiliary variables) are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

getRowTypeGLPK *Retrieve Row Type*

Description

Low level interface function to the GLPK function `glp_get_row_type`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowTypeGLPK(lp, i)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getRowType` which calls the GLPK function `glp_get_row_type`.

Value

The type of the `i`-th row (the corresponding auxiliary variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

getRowUppBndGLPK *Retrieve Row Upper Bound*

Description

Low level interface function to the GLPK function `glp_get_row_ub`. Consult the GLPK documentation for more detailed information.

Usage

```
getRowUppBndGLPK(lp, i)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.

Details

Interface to the C function `getRowUppBnd` which calls the GLPK function `glp_get_row_ub`.

Value

The upper bound of the `i`-th row (the corresponding auxiliary variable) is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`getSimplexParmGLPK` *Retrives the Control Parameters for the Simplex Method.*

Description

Returns the names and values of members in the structure `glp_smcp`. Consult the GLPK documentation for more detailed information.

Usage

```
getSimplexParmGLPK()
```

Details

Interface to the C function `getSimplexParm`.

Value

The function returns a list.

`integer`	The names and corresponding values of all integer control parameters in `glp_smcp`.
`double`	The names and corresponding values of all double control parameters in `glp_smcp`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'Control Parameters'.

`getSjjGLPK` *Retrieve column scale factor*

Description

Low level interface function to the GLPK function `glp_get_sjj`. Consult the GLPK documentation for more detailed information.

Usage

```
getSjjGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.

Details

Interface to the C function `getSjj` which calls the GLPK function `glp_get_sjj`.

Value

Returns the current scale factor s_jj for column `j` of the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

getSolStatGLPK *Determine Generic Status of the Basic Soluton*

Description

Low level interface function to the GLPK function `glp_get_status`. Consult the GLPK documentation for more detailed information.

Usage

```
getSolStatGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getSolStat` which calls the GLPK function `glp_get_status`.

Value

Returns the generic status of the current basic solution for the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

getSolStatIptGLPK *Determine Solution Status*

Description

Low level interface function to the GLPK function `glp_ipt_status`. Consult the GLPK documentation for more detailed information.

Usage

```
getSolStatIptGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getSolStatIpt` which calls the GLPK function `glp_ipt_status`.

Value

Returns the generic status of the current basic solution for the specified problem object.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

getUnbndRayGLPK *Determine Variable Causing Unboundedness*

Description

Low level interface function to the GLPK function `glp_get_unbnd_ray`. Consult the GLPK documentation for more detailed information.

Usage

```
getUnbndRayGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `getUnbndRay` which calls the GLPK function `glp_get_unbnd_ray`.

Value

Returns the number k of a variable, which causes primal or dual unboundedness.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

glpkConstants *Constants, Return and Status Codes of GLPK*

Description

This is a list containing constants used by GLPK. Cunsult the glpk manual for more information, in praticular for the control parameters.

Control Parameters

Simplex

MSG_LEV <- 101	Message level for terminal output (default: GLP_MSG_ALL).
METH <- 102	Simplex method option (default: GLP_PRIMAL).
PRICING <- 103	Pricing technique (default: GLP_PT_PSE).
R_TEST <- 104	Ratio test technique (default: GLP_RT_HAR).
IT_LIM <- 105	Simplex iteration limit (default: INT_MAX).
TM_LIM <- 106	Searching time limit, in milliseconds (default: INT_MAX).
OUT_FRQ <- 107	Output frequency, in iterations (default: 500).
OUT_DLY <- 108	Output delay, in milliseconds (default: 0).
PRESOLVE <- 109	LP presolver option (default: GLP_OFF).
TOL_BND <- 201	Tolerance used to check if the basic solution is primal feasible (default: 1e-7).
TOL_DJ <- 202	Tolerance used to check if the basic solution is dual feasible (default: 1e-7).
TOL_PIV <- 203	Tolerance used to choose eligble pivotal elements of the simplex table (default: 1e-10).
OBJ_LL <- 204	Lower limit of the objective function (default: -DBL_MAX).
OBJ_UL <- 205	Upper limit of the objective function (default: DBL_MAX).

The exact simplex method uses only the parameters IT_LIM and TM_LIM.

Interior

MSG_LEV <- 101	Message level for terminal output (default: GLP_MSG_ALL).
ORD_ALG <- 301	Ordering algorithm used prior to Cholesky factorization (default: GLP_ORD_AMD).

MIP

MSG_LEV <- 101	Message level for terminal output (default: GLP_MSG_ALL).
TM_LIM <- 106	Searching time limit, in milliseconds (default: INT_MAX).
OUT_FRQ <- 107	Output frequency, in iterations (default: 5000).
OUT_DLY <- 108	Output delay, in milliseconds (default: 10000).
PRESOLVE <- 109	MIP presolver option (default: GLP_OFF).
BR_TECH <- 601	Branching technique option (default: GLP_BR_DTH).
BT_TECH <- 602	Backtracking technique option (default: GLP_BT_BLB).
PP_TECH <- 603	Preprocessing technique option (default: GLP_PP_ALL).
FP_HEUR <- 604	Feasibility pump heuristic option (default: GLP_OFF).

GMI_CUTS <- 605	Gomory's mixed integer cut option (default: GLP_OFF).
MIR_CUTS <- 606	Mixed integer rounding (MIR) cut option (default: GLP_OFF).
COV_CUTS <- 607	Mixed cover cut option (default: GLP_OFF).
CLQ_CUTS <- 608	Clique cut option (default: GLP_OFF).
CB_SIZE <- 609	The number of extra (up to 256) bytes allocated for each node of the branch-and-bound tree to store applic
BINARIZE <- 610	LP presolver option (default: GLP_OFF).
CB_FUNC <- 651	Use a user defined callback routine glpkCallback which is written in the file 'glpkCallback.c'. This fil
TOL_INT <- 701	Absolute tolerance used to check if optimal solution to the current LP relaxation is integer feasible (defaul
TOL_OBJ <- 702	Relative tolerance used to check if the objective value in optimal solution to the current LP relaxation is n
MIP_GAP <- 703	The relative mip gap tolerance. If the relative mip gap for currently known best integer feasible solution fa

Basis Factorization

TYPE <- 401	Basis factorization type (default: GLP_BF_FT).
LU_SIZE <- 402	Initial size of the Sparse Vector Area (default: 0).
PIV_LIM <- 403	computing LU-factorization of the basis matrix (default: 4).
SUHL <- 404	computing LU-factorization of the basis matrix (default: GLP_ON).
NFS_MAX <- 405	Maximal number of additional row-like factors (default: 100).
NRS_MAX <- 406	Maximal number of additional rows and columns (default: 100).
RS_SIZE <- 407	Initial size of the Sparse Vector Area (default: 0).
PIV_TOL <- 501	Threshold pivoting (Markowitz) tolerance (default: 0.10).
EPS_TOL <- 502	Epsilon tolerance (default: 1e-15).
MAX_GRO <- 503	Maximal growth of elements of factor U (default: 1e+10).
UPD_TOL <- 504	Update tolerance (default: 1e-6).

LP/MIP problem object

optimization direction flag

GLP_MIN <- 1	minimization
GLP_MAX <- 2	maximization

kind of structural variable

GLP_CV <- 1	continuous variable
GLP_IV <- 2	integer variable
GLP_BV <- 3	binary variable

type of auxiliary/structural variable

GLP_FR <- 1	free variable
GLP_LO <- 2	variable with lower bound
GLP_UP <- 3	variable with upper bound

GLP_DB <- 4	double-bounded variable
GLP_FX <- 5	fixed variable

status of auxiliary/structural variable

GLP_BS <- 1	basic variable
GLP_NL <- 2	non-basic variable on lower bound
GLP_NU <- 3	non-basic variable on upper bound
GLP_NF <- 4	non-basic free variable
GLP_NS <- 5	non-basic fixed variable

scaling options

GLP_SF_GM <- 0x01	perform geometric mean scaling
GLP_SF_EQ <- 0x10	perform equilibration scaling
GLP_SF_2N <- 0x20	round scale factors to power of two
GLP_SF_SKIP <- 0x40	skip if problem is well scaled
GLP_SF_AUTO <- 0x80	choose scaling options automatically

solution indicator

GLP_SOL <- 1	basic solution
GLP_IPT <- 2	interior-point solution
GLP_MIP <- 3	mixed integer solution

solution status

GLP_UNDEF <- 1	solution is undefined
GLP_FEAS <- 2	solution is feasible
GLP_INFEAS <- 3	solution is infeasible
GLP_NOFEAS <- 4	no feasible solution exists
GLP_OPT <- 5	solution is optimal
GLP_UNBND <- 6	solution is unbounded

basis factorization control parameters

type

GLP_BF_FT <- 0x01	LUF + Forrest-Tomlin
GLP_BF_BG <- 0x02	LUF + Schur compl. + Bartels-Golub
GLP_BF_GR <- 0x03	LUF + Schur compl. + Givens rotation
GLP_BF_LUF <- 0x00	plain LU-factorization

GLP_BF_BTF <- 0x10	block triangular LU-factorization

simplex method control parameters

msg_lev message level:

GLP_MSG_OFF <- 0	no output
GLP_MSG_ERR <- 1	warning and error messages only
GLP_MSG_ON <- 2	normal output
GLP_MSG_ALL <- 3	full output
GLP_MSG_DBG <- 4	debug output

meth simplex method option:

GLP_PRIMAL <- 1	use primal simplex
GLP_DUALP <- 2	use dual; if it fails, use primal
GLP_DUAL <- 3	use dual simplex

pricing pricing technique:

GLP_PT_STD <- 0x11	standard (Dantzig rule)
GLP_PT_PSE <- 0x22	projected steepest edge

r_test ratio test technique:

GLP_RT_STD <- 0x11	standard (textbook)
GLP_RT_HAR <- 0x22	two-pass Harris' ratio test

interior-point solver control parameters

ord_alg ordering algorithm:

GLP_ORD_NONE <- 0	natural (original) ordering
GLP_ORD_QMD <- 1	quotient minimum degree (QMD)
GLP_ORD_AMD <- 2	approx. minimum degree (AMD)
GLP_ORD_SYMAMD <- 3	approx. minimum degree (SYMAMD)

integer optimizer control parameters

br_tech branching technique:

GLP_BR_FFV <- 1	first fractional variable
GLP_BR_LFV <- 2	last fractional variable
GLP_BR_MFV <- 3	most fractional variable
GLP_BR_DTH <- 4	heuristic by Driebeck and Tomlin
GLP_BR_HPC <- 5	hybrid pseudocost

bt_tech backtracking technique:

GLP_BT_DFS <- 1	depth first search
GLP_BT_BFS <- 2	breadth first search
GLP_BT_BLB <- 3	best local bound
GLP_BT_BPH <- 4	best projection heuristic

pp_tech preprocessing technique:

GLP_PP_NONE <- 0	disable preprocessing
GLP_PP_ROOT <- 1	preprocessing only on root level
GLP_PP_ALL <- 2	preprocessing on all levels

additional row attributes

the row origin flag

GLP_RF_REG <- 0	regular constraint
GLP_RF_LAZY <- 1	"lazy" constraint
GLP_RF_CUT <- 2	cutting plane constraint

the row class descriptor klass

GLP_RF_GMI <- 1	Gomory's mixed integer cut
GLP_RF_MIR <- 2	mixed integer rounding cut
GLP_RF_COV <- 3	mixed cover cut
GLP_RF_CLQ <- 4	clique cut

enable/disable flag

GLP_ON <- 1	enable something
GLP_OFF <- 0	disable something

reason codes

GLP_IROWGEN <- 0x01	request for row generation
GLP_IBINGO <- 0x02	better integer solution found
GLP_IHEUR <- 0x03	request for heuristic solution
GLP_ICUTGEN <- 0x04	request for cut generation
GLP_IBRANCH <- 0x05	request for branching
GLP_ISELECT <- 0x06	request for subproblem selection
GLP_IPREPRO <- 0x07	request for preprocessing

branch selection indicator

GLP_NO_BRNCH <- 0	select no branch
GLP_DN_BRNCH <- 1	select down-branch
GLP_UP_BRNCH <- 2	select up-branch

return codes

GLP_EBADB <- 0x01	invalid basis
GLP_ESING <- 0x02	singular matrix
GLP_ECOND <- 0x03	ill-conditioned matrix
GLP_EBOUND <- 0x04	invalid bounds
GLP_EFAIL <- 0x05	solver failed
GLP_EOBJLL <- 0x06	objective lower limit reached
GLP_EOBJUL <- 0x07	objective upper limit reached
GLP_EITLIM <- 0x08	iteration limit exceeded
GLP_ETMLIM <- 0x09	time limit exceeded
GLP_ENOPFS <- 0x0A	no primal feasible solution
GLP_ENODFS <- 0x0B	no dual feasible solution
GLP_EROOT <- 0x0C	root LP optimum not provided
GLP_ESTOP <- 0x0D	search terminated by application
GLP_EMIPGAP <- 0x0E	relative mip gap tolerance reached
GLP_ENOFEAS <- 0x0F	no primal/dual feasible solution
GLP_ENOCVG <- 0x10	no convergence
GLP_EINSTAB <- 0x11	numerical instability
GLP_EDATA <- 0x12	invalid data
GLP_ERANGE <- 0x13	result out of range

condition indicator

GLP_KKT_PE <- 1	primal equalities
GLP_KKT_PB <- 2	primal bounds
GLP_KKT_DE <- 3	dual equalities
GLP_KKT_DB <- 4	dual bounds
GLP_KKT_CS <- 5	complementary slackness

MPS file format

GLP_MPS_DECK <- 1	fixed (ancient)
GLP_MPS_FILE <- 2	free (modern)

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

status_codeGLPK, return_codeGLPK

---

glpkPtr-class *Class* "glpkPtr"

Description

Structure of the class "glpkPtr". Objects of that class are used to hold pointers to C structures used by GLPK.

Objects from the Class

Objects can be created by calls of the form
test <- initProbGLPK() or
test <- mplAllocWkspGLPK().

Slots

`glpkPtrType`: Object of class `"character"` giving the pointer type.

`glpkPointer`: Object of class `"externalptr"` containig the pointer to a C structure.

Methods

isGLPKpointer `signature(object = "glpkPtr")`: returns `TRUE` if `glpkPointer(object)` is a pointer to a GLPK problem object, otherwise `FALSE`.

isNULLpointerGLPK `signature(object = "glpkPtr")`: returns `TRUE` if `glpkPointer(object)` is a NULL pointer, otherwise `FALSE`.

isTRWKSpointer `signature(object = "glpkPtr")`: returns `TRUE` if `glpkPointer(object)` is a pointer to a MathProg translator workspace, otherwise `FALSE`.

glpkPointer `signature(object = "glpkPtr")`: gets the `glpkPointer` slot.

glpkPtrType `signature(object = "glpkPtr")`: gets the `glpkPtrType` slot.

glpkPtrType<- `signature(object = "glpkPtr")`: sets the `glpkPtrType` slot.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`mplAllocWkspGLPK` and `initProbGLPK`.

Examples

```
showClass("glpkPtr")
```

`initProbGLPK` *Create a GLPK Problem Object*

Description

Low level interface function to the GLPK function `glp_create_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
initProbGLPK(ptrtype = "glpk_prob")
```

Arguments

ptrtype	A name for the pointer to a GLPK problem object.

Details

Interface to the C function `initProb` which calls the GLPK function `glp_create_prob`.

Value

An instance of class "glpkPtr".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

"glpkPtr".

---

loadMatrixGLPK *Load/Replace the Whole Constraint Matrix*

Description

Low level interface function to the GLPK function `glp_load_matrix`. Consult the GLPK documentation for more detailed information.

Usage

```
loadMatrixGLPK(lp, ne, ia, ja, ra)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
ne	Number of non-zero elements.
ia	Row indices of the non-zero elements.
ja	Colunm indices of the non-zero elements.
ra	The numeric values of the constraint coefficients.

Details

Interface to the C function `loadMatrix` which calls the GLPK function `glp_load_matrix`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

mipColsValGLPK *Retrieve Column Value of all Columns*

Description

This is an advanced version of `mipColValGLPK`.

Usage

```
mipColsValGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `mipColsVal` which calls the GLPK function `glp_mip_col_val`.

Value

The column values of all columns are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`mipColValGLPK` *Retrieve Column Value*

Description

Low level interface function to the GLPK function `glp_mip_col_val`. Consult the GLPK documentation for more detailed information.

Usage

```
mipColValGLPK(lp, j)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.

Details

Interface to the C function `mipColVal` which calls the GLPK function `glp_mip_col_val`.

Value

Column value of column `j`.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

mipObjValGLPK *Retrieve Objective Value*

Description

Low level interface function to the GLPK function `glp_mip_obj_val`. Consult the GLPK documentation for more detailed information.

Usage

```
mipObjValGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `mipObjVal` which calls the GLPK function `glp_mip_obj_val`.

Value

Objective value.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

mipRowsValGLPK *Retrieve Row Value of all Rows*

Description

This is an advanced version of `mipRowValGLPK`.

Usage

```
mipRowsValGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function mipRowsVal which calls the GLPK function glp_mip_row_val.

Value

The row values of all rows are returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

mipRowValGLPK *Retrieve Row Value*

Description

Low level interface function to the GLPK function glp_mip_row_val. Consult the GLPK documentation for more detailed information.

Usage

```
mipRowValGLPK(lp, i)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Row number i.

Details

Interface to the C function mipRowVal which calls the GLPK function glp_mip_row_val.

Value

Row value of row i.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`mipStatusGLPK` *Determine Status of MIP Solution*

Description

Low level interface function to the GLPK function `glp_mip_status`. Consult the GLPK documentation for more detailed information.

Usage

```
mipStatusGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `mipStatus` which calls the GLPK function `glp_mip_status`.

Value

Status of MIP Solution.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

mplAllocWkspGLPK *Allocate Translator Workspace*

Description

Low level interface function to the GLPK function `glp_mpl_alloc_wksp`. Consult the GLPK documentation for more detailed information.

Usage

```
mplAllocWkspGLPK(ptrtype = "tr_wksp")
```

Arguments

`ptrtype`	A name for the pointer to a translator workspace.

Details

Interface to the C function `mplAllocWksp` which calls the GLPK function `glp_mpl_alloc_wksp`.

Value

An instance of class "`glpkPtr`".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

"`glpkPtr`".

mplBuildProbGLPK *Build Problem Instance From Model*

Description

Low level interface function to the GLPK function `glp_mpl_build_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
mplBuildProbGLPK(wk, lp)
```

Arguments

`wk`	An object of class `"glpkPtr"` as returned by `mplAllocWkspGLPK`. This is basically a pointer to a GLPK translocator workspace.
`lp`	A pointer to a GLPK problem object.

Details

Interface to the C function `mplBuildProb` which calls the GLPK function `glp_mpl_build_prob`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`mplAllocWkspGLPK`, `mplFreeWkspGLPK`, `mplGenerateGLPK`, `mplPostsolveGLPK`, `mplReadDataGLPK` and `mplReadModelGLPK`.

mplFreeWkspGLPK *Free Translator Workspace*

Description

Low level interface function to the GLPK function glp_mpl_free_wksp. Consult the GLPK documentation for more detailed information.

Usage

```
mplFreeWkspGLPK(wk)
```

Arguments

wk	An object of class "glpkPtr" as returned by mplAllocWkspGLPK. This is basically a pointer to a GLPK translocator workspace.

Details

Interface to the C function mplFreeWksp which calls the GLPK function glp_mpl_free_wksp.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

mplAllocWkspGLPK, mplBuildProbGLPK, mplGenerateGLPK, mplPostsolveGLPK, mplReadDataGLPK and mplReadModelGLPK.

mplGenerateGLPK *Generate the Model*

Description

Low level interface function to the GLPK function `glp_mpl_generate`. Consult the GLPK documentation for more detailed information.

Usage

```
mplGenerateGLPK(wk, fname = NULL)
```

Arguments

`wk`	An object of class `"glpkPtr"` as returned by `mplAllocWkspGLPK`. This is basically a pointer to a GLPK translocator workspace.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `mplGenerate` which calls the GLPK function `glp_mpl_generate`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`mplAllocWkspGLPK`, `mplBuildProbGLPK`, `mplFreeWkspGLPK`, `mplPostsolveGLPK`, `mplReadDataGLPK` and `mplReadModelGLPK`.

mplPostsolveGLPK *Postsolve Model*

Description

Low level interface function to the GLPK function glp_mpl_postsolve. Consult the GLPK documentation for more detailed information.

Usage

```
mplPostsolveGLPK(wk, lp, sol)
```

Arguments

wk	An object of class "glpkPtr" as returned by mplAllocWkspGLPK. This is basically a pointer to a GLPK translocator workspace.
lp	A pointer to a GLPK problem object.
sol	Type of solution to be copied to the translator workspace, for possible values, see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function mplPostsolve which calls the GLPK function glp_mpl_postsolve.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

mplAllocWkspGLPK, mplBuildProbGLPK, mplFreeWkspGLPK, mplGenerateGLPK, mplReadDataGLPK and mplReadModelGLPK.

`mplReadDataGLPK` *Read and Translate Data Section*

Description

Low level interface function to the GLPK function `glp_mpl_read_data`. Consult the GLPK documentation for more detailed information.

Usage

```
mplReadDataGLPK(wk, fname)
```

Arguments

`wk`	An object of class `"glpkPtr"` as returned by `mplAllocWkspGLPK`. This is basically a pointer to a GLPK translocator workspace.
`fname`	The name of the data file to be read in.

Details

Interface to the C function `mplReadData` which calls the GLPK function `glp_mpl_read_data`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`mplAllocWkspGLPK`, `mplBuildProbGLPK`, `mplFreeWkspGLPK`, `mplGenerateGLPK`, `mplPostsolveGLPK` and `mplReadModelGLPK`.

`mplReadModelGLPK` *Read and Translate Model Section*

Description

Low level interface function to the GLPK function `glp_mpl_read_model`. Consult the GLPK documentation for more detailed information.

Usage

```
mplReadModelGLPK(wk, fname, skip)
```

Arguments

`wk`	An object of class `"glpkPtr"` as returned by `mplAllocWkspGLPK`. This is basically a pointer to a GLPK translocator workspace.
`fname`	The name of the model file to be read in.
`skip`	Flag, how to treat the data section.

Details

Interface to the C function `mplReadModel` which calls the GLPK function `glp_mpl_read_model`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`mplAllocWkspGLPK`, `mplBuildProbGLPK`, `mplFreeWkspGLPK`, `mplGenerateGLPK`, `mplPostsolveGLPK` and `mplReadDataGLPK`.

printIptGLPK *Write Interior-Point Solution in Printable Format*

Description

Low level interface function to the GLPK function `glp_print_ipt`. Consult the GLPK documentation for more detailed information.

Usage

```
printIptGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `printIpt` which calls the GLPK function `glp_print_ipt`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

printMIPGLPK *Write Interior-Point Solution in Printable Format*

Description

Low level interface function to the GLPK function `glp_print_mip`. Consult the GLPK documentation for more detailed information.

Usage

```
printMIPGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `printMIP` which calls the GLPK function `glp_print_mip`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

printRangesGLPK *Print Sensitivity Analysis Report*

Description

Low level interface function to the GLPK function `glp_print_ranges`. Consult the GLPK documentation for more detailed information.

Usage

```
printRangesGLPK(lp, numrc = 0, rowcol = NULL, fname = "sar.txt")
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`numrc`	Length of the row/column list (argument `rowcol`).
`rowcol`	Ordinal numbers of rows and columns to be analyzed.
`fname`	A filename.

Details

Interface to the C function `printRanges` which calls the GLPK function `glp_print_ranges`.

Value

Zero on success, otherwise non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

printSolGLPK *Write Basic Solution in Printable Format*

Description

Low level interface function to the GLPK function `glp_print_sol`. Consult the GLPK documentation for more detailed information.

Usage

```
printSolGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `printSol` which calls the GLPK function `glp_print_sol`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

readIptGLPK *Read Interior-Point Solution From Text File*

Description

Low level interface function to the GLPK function `glp_read_ipt`. Consult the GLPK documentation for more detailed information.

Usage

```
readIptGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readIpt` which calls the GLPK function `glp_read_ipt`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `writeIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

readLPGLPK *Read Problem Data in CPLEX LP Format*

Description

Low level interface function to the GLPK function `glp_read_lp`. Consult the GLPK documentation for more detailed information.

Usage

```
readLPGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readLP` which calls the GLPK function `glp_read_lp`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`readMPSGLPK`, `readProbGLPK`, `writeMPSGLPK`, `writeLPGLPK` and `writeProbGLPK`.

readMIPGLPK *Read MIP Solution From Text File*

Description

Low level interface function to the GLPK function `glp_read_mip`. Consult the GLPK documentation for more detailed information.

Usage

```
readMIPGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readMIP` which calls the GLPK function `glp_read_mip`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK` and `writeMIPGLPK`.

readMPSGLPK *Read Problem Data in MPS Format*

Description

Low level interface function to the GLPK function `glp_read_mps`. Consult the GLPK documentation for more detailed information.

Usage

```
readMPSGLPK(lp, fmt, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fmt`	MPS format. See `glpkConstants`, section 'MPS file formats'.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readMPS` which calls the GLPK function `glp_read_mps`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readLPGLPK`, `readProbGLPK`, `writeMPSGLPK`, `writeLPGLPK`, `writeProbGLPK` and `glpkConstants`.

readProbGLPK *Read Problem Data in GLPK F ormat*

Description

Low level interface function to the GLPK function `glp_read_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
readProbGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readProb` which calls the GLPK function `glp_read_prob`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readMPSGLPK`, `readLPGLPK`, `writeMPSGLPK`, `writeLPGLPK` and `writeProbGLPK`.

readSolGLPK *Read Basic Solution From Text File*

Description

Low level interface function to the GLPK function `glp_read_sol`. Consult the GLPK documentation for more detailed information.

Usage

```
readSolGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be read in.

Details

Interface to the C function `readSol` which calls the GLPK function `glp_read_sol`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

return_codeGLPK *Translates a GLPK Return Code into a Human Readable String*

Description

Translates a GLPK return code into a human readable string.

Usage

```
return_codeGLPK(code)
```

Arguments

code	Return code from GLPK.

Value

A character string associated with the GLPK return code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'return codes'.

scaleProbGLPK *Scale Problem Data*

Description

Low level interface function to the GLPK function glp_scale_prob. Consult the GLPK documentation for more detailed information.

Usage

```
scaleProbGLPK(lp, opt)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`opt`	Scaling option, see `glpkConstants`, section 'LP/MIP problem object' for possible values.

Details

Interface to the C function `scaleProb` which calls the GLPK function `glp_scale_prob`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`

`setBfcpGLPK` *Change Basis Factorization Control Parameters*

Description

Sets/Changes the values of corresponding members of in the structure `glp_bfcp`. Consult the GLPK documentation for more detailed information.

Usage

```
setBfcpGLPK(lp, parm, val)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`parm`	A vector containing integer values or symbolic names of the control parameters to be changed (see `glpkConstants`, section 'Control Parameters').
`val`	A vector containing the new values for the corresponding control parameters.

Details

The Arguments `parm` and `val` must have the same length. The value `val[i]` belongs to the parameter `parm[i]`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`

`setColBndGLPK` *Set/Change Column Bounds*

Description

Low level interface function to the GLPK function `glp_set_col_bnds`. Consult the GLPK documentation for more detailed information.

Usage

```
setColBndGLPK(lp, j, type, lb, ub)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.
`type`	Column type. For possible values, see `glpkConstants`, section 'LP/MIP problem object'.
`lb`	Lower bound.
`ub`	Upper bound.

Details

Interface to the C function `setColBnd` which calls the GLPK function `glp_set_col_bnds`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setColKindGLPK *Set Column Kind*

Description

Low level interface function to the GLPK function `glp_set_col_kind`. Consult the GLPK documentation for more detailed information.

Usage

```
setColKindGLPK(lp, j, kind)
```

Arguments

`lp`	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
`j`	Column number `j`.
`kind`	Kind of column number `j`, for possible values see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function `setColKind` which calls the GLPK function `glp_set_col_kind`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setColNameGLPK *Set/Change Column Name*

Description

Low level interface function to the GLPK function glp_set_col_name. Consult the GLPK documentation for more detailed information.

Usage

```
setColNameGLPK(lp, j, cname = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Column number j.
cname	Column name.

Details

Interface to the C function setColName which calls the GLPK function glp_set_col_name.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

setColsBndsGLPK *Set/Change Column Bounds*

Description

This is an advanced version of setColBndGLPK. Here, j can be an integer vector, lb and ub can be numeric vectors.

Usage

```
setColsBndsGLPK(lp, j, lb, ub, type = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Vector of column numbers.
lb	Vector of lower bounds.
ub	Vector of upper bounds.
type	Vector of variable types (default: NULL). For possible values, see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function setColsBnds which calls the GLPK function glp_set_col_bnds.

If type is set to NULL, the type of the variables will be estimated. If lb[i] equals ub[i], variable j[i] is fixed, otherwise double bounded.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setColsBndsObjCoefsGLPK

Set/Change Column Bounds and Objective Coefficients and/or Constant Term

---

Description

This is an combined version of setColsBndsGLPK and setObjCoefsGLPK. Here, j can be an integer vector, lb, ub and obj_coef can be numeric vectors.

Usage

```
setColsBndsObjCoefsGLPK(lp, j, lb, ub, obj_coef, type = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Vector of column numbers.
lb	Vector of lower bounds.
ub	Vector of upper bounds.
obj_coef	Vector of objective coefficients.
type	Vector of variable types (default: NULL). For possible values, see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function setColsBndsObjCoefs which calls the GLPK functions glp_set_col_bnds and glp_set_obj_coef.

If type is set to NULL, the type of the variables will be estimated. If lb[i] equals ub[i], variable j[i] is fixed, otherwise double bounded.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setColsKindGLPK *Set Column Kind for a Set of Columns*

Description

This is an advanced version of setColKindGLPK. Here, j can be an integer vector.

Usage

```
setColsKindGLPK(lp, j, kind)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	An integer vector of column indices.
kind	An integer vector of column kinds, for possible values see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function setColsKind which calls the GLPK function glp_set_col_kind.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

`setColsNamesGLPK` *Set/Change Column Names*

Description

This is an advanced version of setColNameGLPK. Here, `j` can be an integer vector, `cnames` can be a character vector.

Usage

```
setColsNamesGLPK(lp, j, cnames = NULL)
```

Arguments

`lp`	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
`j`	Vector of column numbers.
`cnames`	Vector of column names of the same length as `j` or `NULL`.

Details

Interface to the C function `setColsNames` which calls the GLPK function `glp_set_col_name`.

If `cnames` is set to `NULL`, all column names for column indices in `j` will be removed. If `cname[k]` is the empty string `""`, column name `j[k]` will be removed.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`setColStatGLPK` *Set column status*

Description

Low level interface function to the GLPK function `glp_set_col_stat`. Consult the GLPK documentation for more detailed information.

Usage

```
setColStatGLPK(lp, j, stat)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.
`stat`	A status parameter, see `glpkConstants`, section 'LP/MIP problem object' for possible values.

Details

Interface to the C function `setColStat` which calls the GLPK function `glp_set_col_stat`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`

setDefaultIptParmGLPK *Sets the Default Control Parameters for the Interior-point Method.*

Description

Initializes a new structure `glp_iptcp`. Consult the GLPK documentation for more detailed information.

Usage

```
setDefaultIptParmGLPK()
```

Details

Interface to the C function `setDefaultIptParm` which calls the GLPK function `glp_init_iptcp`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'Control Parameters'.

setDefaultMIPParmGLPK *Sets the Default Control Parameters for the MIP Method*

Description

Initializes a new structure `glp_iocp`. Consult the GLPK documentation for more detailed information.

Usage

```
setDefaultMIPParmGLPK()
```

Details

Interface to the C function `setDefaultMIPParm` which calls the GLPK function `glp_init_iocp`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`, section 'Control Parameters'.

---

setDefaultSmpParmGLPK *Sets the Default Control Parameters for the Simplex Methods.*

Description

Initializes a new structure `glp_smcp`. Consult the GLPK documentation for more detailed information.

Usage

```
setDefaultSmpParmGLPK()
```

Details

Interface to the C function `setDefaultSmpParm` which calls the GLPK function `glp_init_smcp`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'Control Parameters'.

`setInteriorParmGLPK` *Sets/Changes Control Parameters or the Interior-point Method.*

Description

Sets/Changes the values of corresponding members of in the structure `glp_iptcp`. Consult the GLPK documentation for more detailed information.

Usage

```
setInteriorParmGLPK(parm, val)
```

Arguments

`parm`	A vector containing integer values or symbolic names of the control parameters to be changed (see glpkConstants, section 'Control Parameters') and 'interior-point solver control parameters').
`val`	A vector containing the new values for the corresponding control parameters.

Details

The Arguments `parm` and `val` must have the same length. The value `val[i]` belongs to the parameter `parm[i]`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setMatColGLPK *Set (Replace) Column of the Constraint Matrix*

Description

Low level interface function to the GLPK function glp_set_mat_col. Consult the GLPK documentation for more detailed information.

Usage

```
setMatColGLPK(lp, j, len, ind, val)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Replace the j-th column of the constraint matrix of the specified problem object.
len	Number of new column elements.
ind	Row indices of the new column elements.
val	Numerical values of the new column elements.

Details

Interface to the C function setMatCol which calls the GLPK function glp_set_mat_col.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

setMatRowGLPK *Set (Replace) Row of the Constraint Matrix*

Description

Low level interface function to the GLPK function `glp_set_mat_row`. Consult the GLPK documentation for more detailed information.

Usage

```
setMatRowGLPK(lp, i, len, ind, val)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Replace the `i`-th row of the constraint matrix of the specified problem object.
`len`	Number of new row elements.
`ind`	Column indices of the new row elements.
`val`	Numerical values of the new row elements.

Details

Interface to the C function `setMatRow` which calls the GLPK function `glp_set_mat_row`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

setMIPParmGLPK *Sets/Changes Control Parameters or the MIP Methods*

Description

Sets/Changes the values of corresponding members of in the structure glp_iocp. Consult the GLPK documentation for more detailed information.

Usage

```
setMIPParmGLPK(parm, val)
```

Arguments

parm	A vector containing integer values or symbolic names of the control parameters to be changed (see glpkConstants, section 'Control Parameters' and 'integer optimizer control parameters').
val	A vector containing the new values for the corresponding control parameters.

Details

The Arguments parm and val must have the same length. The value val[i] belongs to the parameter parm[i].

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

setObjCoefGLPK *Set/Change Objective Coefficient or Constant Term*

Description

Low level interface function to the GLPK function `glp_set_obj_coef`. Consult the GLPK documentation for more detailed information.

Usage

```
setObjCoefGLPK(lp, j, obj_coef)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.
`obj_coef`	Objective coefficient or constant term.

Details

Interface to the C function `setObjCoef` which calls the GLPK function `glp_set_obj_coef`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

setObjCoefsGLPK *Set/Change Objective Coefficients and/or Constant Term*

Description

This is an advanced version of setColBndGLPK. Here, j can be an integer vector, obj_coef can be a numeric vector.

Usage

```
setObjCoefsGLPK(lp, j, obj_coef)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
j	Vector of column numbers.
obj_coef	Vector of objective coefficients.

Details

Interface to the C function setObjCoefs which calls the GLPK function glp_set_obj_coef.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

setObjDirGLPK *Set/Change Optimization Direction Flag*

Description

Low level interface function to the GLPK function `glp_set_obj_dir`. Consult the GLPK documentation for more detailed information.

Usage

```
setObjDirGLPK(lp, lpdir)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`lpdir`	Optimization direction flag, which can be `GLP_MIN` (default) or `GLP_MAX`.

Details

Interface to the C function `setObjDir` which calls the GLPK function `glp_set_obj_dir`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'LP/MIP problem object'.

setObjNameGLPK *Set/Change Objective Function Name*

Description

Low level interface function to the GLPK function `glp_set_obj_name`. Consult the GLPK documentation for more detailed information.

Usage

```
setObjNameGLPK(lp, oname = NULL)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`oname`	Objective Function name.

Details

Interface to the C function `setObjName` which calls the GLPK function `glp_set_obj_name`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

setProbNameGLPK *Set/Change Problem Name*

Description

Low level interface function to the GLPK function glp_set_prob_name. Consult the GLPK documentation for more detailed information.

Usage

```
setProbNameGLPK(lp, pname = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
pname	Problem name.

Details

Interface to the C function setProbName which calls the GLPK function glp_set_prob_name.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

setRhsZeroGLPK *Set/Change all Row Bounds to Zero*

Description

This is an advanced version of `setRowsBndsGLPK`.

Usage

```
setRhsZeroGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `setRowsBnds` which calls the GLPK function `glp_set_col_bnds`. All row bounds are fixed at zero.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

setRiiGLPK *Set row scale factor*

Description

Low level interface function to the GLPK function `glp_set_rii`. Consult the GLPK documentation for more detailed information.

Usage

```
setRiiGLPK(lp, i, rii)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Row number i.
rii	Scale factor r_ii.

Details

Interface to the C function setRii which calls the GLPK function glp_set_rii.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

setRowBndGLPK *Set/Change Row Bounds*

Description

Low level interface function to the GLPK function glp_set_row_bnds. Consult the GLPK documentation for more detailed information.

Usage

```
setRowBndGLPK(lp, i, type, lb, ub)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Row number i.
type	Row type. For possible values, see glpkConstants, section 'LP/MIP problem object'.
lb	Lower bound.
ub	Upper bound.

Details

Interface to the C function `setRowBnd` which calls the GLPK function `glp_set_row_bnds`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

---

setRowNameGLPK *Set/Change Row Name*

Description

Low level interface function to the GLPK function `glp_set_row_name`. Consult the GLPK documentation for more detailed information.

Usage

```
setRowNameGLPK(lp, i, rname = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Row number i.
rname	Row name.

Details

Interface to the C function `setRowName` which calls the GLPK function `glp_set_row_name`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

setRowsBndsGLPK *Set/Change Row Bounds*

Description

This is an advanced version of setRowBndGLPK. Here, i can be an integer vector, lb and ub can be numeric vectors.

Usage

```
setRowsBndsGLPK(lp, i, lb, ub, type = NULL)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
i	Vector of row numbers.
lb	Vector of lower bounds.
ub	Vector of upper bounds.
type	Vector of variable types (default: NULL). For possible values, see glpkConstants, section 'LP/MIP problem object'.

Details

Interface to the C function setRowsBnds which calls the GLPK function glp_set_row_bnds.

If type is set to NULL, the type of the variables will be estimated. If lb[j] equals ub[j], variable i[j] is fixed, otherwise double bounded.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants

`setRowsNamesGLPK` *Set/Change Row Names*

Description

This is an advanced version of setRowNameGLPK. Here, `i` can be an integer vector, `rnames` can be a character vector.

Usage

```
setRowsNamesGLPK(lp, i, rnames = NULL)
```

Arguments

`lp`	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.
`i`	Vector of row numbers.
`rnames`	Vector of row names of the same length as `i` or `NULL`.

Details

Interface to the C function `setRowsNames` which calls the GLPK function `glp_set_row_name`.

If `rnames` is set to `NULL`, all row names for row indices in `i` will be removed. If `rname[k]` is the empty string `""`, row name `i[k]` will be removed.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`setRowStatGLPK` *Set row status*

Description

Low level interface function to the GLPK function `glp_set_row_stat`. Consult the GLPK documentation for more detailed information.

Usage

```
setRowStatGLPK(lp, i, stat)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`i`	Row number i.
`stat`	A status parameter, see `glpkConstants` for possible values.

Details

Interface to the C function `setRowStat` which calls the GLPK function `glp_set_row_stat`, section 'LP/MIP problem object'.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`

`setSimplexParmGLPK` *Sets/Changes Control Parameters or the Simplex Methods.*

Description

Sets/Changes the values of corresponding members of in the structure `glp_smcp`. Consult the GLPK documentation for more detailed information.

Usage

```
setSimplexParmGLPK(parm, val)
```

Arguments

`parm`	A vector containing integer values or symbolic names of the control parameters to be changed (see `glpkConstants`, section 'Control Parameters' and 'simplex method control parameters').
`val`	A vector containing the new values for the corresponding control parameters.

Details

The Arguments `parm` and `val` must have the same length. The value `val[i]` belongs to the parameter `parm[i]`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`

setSjjGLPK *Retrieve column scale factor*

Description

Low level interface function to the GLPK function `glp_set_sjj`. Consult the GLPK documentation for more detailed information.

Usage

```
setSjjGLPK(lp, j, sjj)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`j`	Column number j.
`sjj`	Scale factor s_jj.

Details

Interface to the C function `setSjj` which calls the GLPK function `glp_set_sjj`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

`solveInteriorGLPK` *Solve LP Problem with the Interior-Point Method*

Description

Low level interface function to the GLPK function `glp_interior`. Consult the GLPK documentation for more detailed information.

Usage

```
solveInteriorGLPK(lp)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `solveInterior` which calls the GLPK function `glp_interior`.

Value

A return code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'return codes' and `return_codeGLPK`.

`solveMIPGLPK` *Solve MIP Problem with the Branch-and-Cut Method*

Description

Low level interface function to the GLPK function `glp_intopt`. Consult the GLPK documentation for more detailed information.

Usage

```
solveMIPGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `solveMIP` which calls the GLPK function `glp_intopt`.

Value

A return code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'return codes' and `return_codeGLPK`.

`solveSimplexExactGLPK` *Solve LP Problem in Exact Arithmetic*

Description

Low level interface function to the GLPK function `glp_exact`. Consult the GLPK documentation for more detailed information.

Usage

```
solveSimplexExactGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `solveSimplexExact` which calls the GLPK function `glp_exact`.

Value

A return code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'return codes' and `return_codeGLPK`.

`solveSimplexGLPK` *Solve LP Problem with the Primal or Dual Simplex Method*

Description

Low level interface function to the GLPK function `glp_simplex`. Consult the GLPK documentation for more detailed information.

Usage

```
solveSimplexGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `solveSimplex` which calls the GLPK function `glp_simplex`.

Value

A return code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`glpkConstants`, section 'return codes' and `return_codeGLPK`.

sortMatrixGLPK *Sort Elements of the Constraint Matrix*

Description

Low level interface function to the GLPK function `glp_sort_matrix`. Consult the GLPK documentation for more detailed information.

Usage

```
sortMatrixGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `sortMatrix` which calls the GLPK function `glp_sort_matrix`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

status_codeGLPK *Translates a GLPK Status Value into a Human Readable String*

Description

Translates a GLPK status code into a human readable string.

Usage

```
status_codeGLPK(code)
```

Arguments

code	Status code from GLPK.

Value

A character string associated with the GLPK status code.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

glpkConstants, section 'LP/MIP problem object'.

---

stdBasisGLPK *Contruct Standard Initial LP Basis*

Description

Low level interface function to the GLPK function glp_std_basis. Consult the GLPK documentation for more detailed information.

Usage

```
stdBasisGLPK(lp)
```

Arguments

lp	An object of class "glpkPtr" as returned by initProbGLPK. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function stdBasis which calls the GLPK function glp_std_basis.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

`termOutGLPK` *Enable/Disable Terminal Output*

Description

Low level interface function to the GLPK function `glp_term_out`. Consult the GLPK documentation for more detailed information.

Usage

```
termOutGLPK(flag)
```

Arguments

`flag`	GLPK enable/disable flag: `GLP_ON` or `GLP_OFF`.

Details

Interface to the C function `termOut` which calls the GLPK function `glp_term_out`.

Value

Returns the previous value of the terminal output flag.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`glpkConstants`, section 'enable/disable flag'.

unscaleProbGLPK *Problem unscaling*

Description

Low level interface function to the GLPK function `glp_unscale_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
unscaleProbGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `unscaleProb` which calls the GLPK function `glp_unscale_prob`.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

versionGLPK *Determine GLPK Callable Library Version*

Description

Low level interface function to the GLPK function `glp_version`. Consult the GLPK documentation for more detailed information.

Usage

```
versionGLPK()
```

Details

Interface to the C function `version` which calls the GLPK function `glp_version`.

Value

Returns a single character value containing the GLPK version number.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

---

warmUpGLPK *Warm Up LP Basis*

Description

Low level interface function to the GLPK function `glp_warm_up`. Consult the GLPK documentation for more detailed information.

Usage

```
warmUpGLPK(lp)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.

Details

Interface to the C function `warmUp` which calls the GLPK function `glp_warm_up`.

Value

Status of "warming up".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html

---

`writeIptGLPK` *Write Interior-Point Solution to Text File*

Description

Low level interface function to the GLPK function `glp_write_ipt`. Consult the GLPK documentation for more detailed information.

Usage

```
writeIptGLPK(lp, fname)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeIpt` which calls the GLPK function `glp_write_ipt`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at http://www.gnu.org/software/glpk/glpk.html.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

writeLPGLPK *Write Problem Data in CPLEX LP Format*

Description

Low level interface function to the GLPK function `glp_write_lp`. Consult the GLPK documentation for more detailed information.

Usage

```
writeLPGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeLP` which calls the GLPK function `glp_write_lp`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readMPSGLPK`, `readLPGLPK`, `readProbGLPK`, `writeMPSGLPK` and `writeProbGLPK`.

writeMIPGLPK *Write MIP Solution to Text File*

Description

Low level interface function to the GLPK function `glp_write_mip`. Consult the GLPK documentation for more detailed information.

Usage

```
writeMIPGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeMIP` which calls the GLPK function `glp_write_mip`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `writeSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK` and `readMIPGLPK`.

writeMPSGLPK *Write Problem Data in MPS Format*

Description

Low level interface function to the GLPK function `glp_write_mps`. Consult the GLPK documentation for more detailed information.

Usage

```
writeMPSGLPK(lp, fmt, fname)
```

Arguments

`lp`	An object of class `"glpkPtr"` as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fmt`	MPS format. See `glpkConstants`, section 'MPS file formats'.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeMPS` which calls the GLPK function `glp_write_mps`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readMPSGLPK`, `readLPGLPK`, `readProbGLPK`, `writeLPGLPK`, `writeProbGLPK` and `glpkConstants`.

writeProbGLPK *Write Problem Data in GLPK Format*

Description

Low level interface function to the GLPK function `glp_write_prob`. Consult the GLPK documentation for more detailed information.

Usage

```
writeProbGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeProb` which calls the GLPK function `glp_write_prob`.

Value

Returns zero on success, otherwise it returns non-zero and prints an error message.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`readMPSGLPK`, `readLPGLPK`, `readProbGLPK`, `writeLPGLPK` and `writeMPSGLPK`.

writeSolGLPK *Write Basic Solution to Text File*

Description

Low level interface function to the GLPK function `glp_write_sol`. Consult the GLPK documentation for more detailed information.

Usage

```
writeSolGLPK(lp, fname)
```

Arguments

`lp`	An object of class "`glpkPtr`" as returned by `initProbGLPK`. This is basically a pointer to a GLPK problem object.
`fname`	The name of the text file to be written out.

Details

Interface to the C function `writeSol` which calls the GLPK function `glp_write_sol`.

Value

Returns zero on success, otherwise it returns non-zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Mayo Roettger <mayo.roettger@hhu.de>

References

Based on the package **glpk** by Lopaka Lee.

The GNU GLPK home page at `http://www.gnu.org/software/glpk/glpk.html`.

See Also

`printSolGLPK`, `readSolGLPK`, `printIptGLPK`, `readIptGLPK`, `writeIptGLPK`, `printMIPGLPK`, `readMIPGLPK` and `writeMIPGLPK`.

Index

∗ **optimize**

addColsGLPK, 6
addRowsGLPK, 7
advBasisGLPK, 8
bfExistsGLPK, 9
bfUpdatedGLPK, 10
checkDupGLPK, 11
copyProbGLPK, 12
cpxBasisGLPK, 13
createIndexGLPK, 13
delColsGLPK, 14
deleteIndexGLPK, 15
delProbGLPK, 16
delRowsGLPK, 16
eraseProbGLPK, 17
factorizeGLPK, 18
findColGLPK, 19
findRowGLPK, 20
getBfcpGLPK, 21
getBheadGLPK, 22
getCbindGLPK, 23
getColDualGLPK, 24
getColDualIptGLPK, 25
getColKindGLPK, 26
getColLowBndGLPK, 27
getColNameGLPK, 28
getColPrimGLPK, 29
getColPrimIptGLPK, 30
getColsDualGLPK, 31
getColsDualIptGLPK, 31
getColsKindGLPK, 32
getColsLowBndsGLPK, 33
getColsPrimGLPK, 34
getColsPrimIptGLPK, 34
getColsStatGLPK, 35
getColStatGLPK, 36
getColsUppBndsGLPK, 37
getColTypeGLPK, 38
getColUppBndGLPK, 39
getDualStatGLPK, 40
getInteriorParmGLPK, 41
getMatColGLPK, 42
getMatRowGLPK, 43
getMIPParmGLPK, 44
getNumBinGLPK, 45
getNumColsGLPK, 45
getNumIntGLPK, 46
getNumNnzGLPK, 47
getNumRowsGLPK, 48
getObjCoefGLPK, 48
getObjCoefsGLPK, 49
getObjDirGLPK, 50
getObjNameGLPK, 51
getObjValGLPK, 52
getObjValIptGLPK, 52
getPrimStatGLPK, 53
getProbNameGLPK, 54
getRbindGLPK, 55
getRiiGLPK, 56
getRowDualGLPK, 57
getRowDualIptGLPK, 58
getRowLowBndGLPK, 59
getRowNameGLPK, 60
getRowPrimGLPK, 61
getRowPrimIptGLPK, 62
getRowsDualGLPK, 63
getRowsDualIptGLPK, 63
getRowsLowBndsGLPK, 64
getRowsPrimGLPK, 65
getRowsPrimIptGLPK, 66
getRowsStatGLPK, 66
getRowStatGLPK, 67
getRowsTypesGLPK, 68
getRowsUppBndsGLPK, 69
getRowTypeGLPK, 70
getRowUppBndGLPK, 71
getSimplexParmGLPK, 72
getSjjGLPK, 73

getSolStatGLPK, 74
getSolStatIptGLPK, 75
getUnbndRayGLPK, 76
glpkAPI-package, 5
glpkConstants, 77
glpkPtr-class, 83
initProbGLPK, 84
loadMatrixGLPK, 85
mipColsValGLPK, 86
mipColValGLPK, 87
mipObjValGLPK, 88
mipRowsValGLPK, 88
mipRowValGLPK, 89
mipStatusGLPK, 90
mplAllocWkspGLPK, 91
mplBuildProbGLPK, 92
mplFreeWkspGLPK, 93
mplGenerateGLPK, 94
mplPostsolveGLPK, 95
mplReadDataGLPK, 96
mplReadModelGLPK, 97
printIptGLPK, 98
printMIPGLPK, 99
printRangesGLPK, 100
printSolGLPK, 101
readIptGLPK, 102
readLPGLPK, 103
readMIPGLPK, 104
readMPSGLPK, 105
readProbGLPK, 106
readSolGLPK, 107
return_codeGLPK, 108
scaleProbGLPK, 108
setBfcpGLPK, 109
setColBndGLPK, 110
setColKindGLPK, 111
setColNameGLPK, 112
setColsBndsGLPK, 113
setColsBndsObjCoefsGLPK, 114
setColsKindGLPK, 115
setColsNamesGLPK, 116
setColStatGLPK, 117
setDefaultIptParmGLPK, 118
setDefaultMIPParmGLPK, 118
setDefaultSmpParmGLPK, 119
setInteriorParmGLPK, 120
setMatColGLPK, 121
setMatRowGLPK, 122
setMIPParmGLPK, 123
setObjCoefGLPK, 124
setObjCoefsGLPK, 125
setObjDirGLPK, 126
setObjNameGLPK, 127
setProbNameGLPK, 128
setRhsZeroGLPK, 129
setRiiGLPK, 129
setRowBndGLPK, 130
setRowNameGLPK, 131
setRowsBndsGLPK, 132
setRowsNamesGLPK, 133
setRowStatGLPK, 134
setSimplexParmGLPK, 135
setSjjGLPK, 136
solveInteriorGLPK, 137
solveMIPGLPK, 138
solveSimplexExactGLPK, 139
solveSimplexGLPK, 140
sortMatrixGLPK, 141
status_codeGLPK, 141
stdBasisGLPK, 142
termOutGLPK, 143
unscaleProbGLPK, 144
versionGLPK, 144
warmUpGLPK, 145
writeIptGLPK, 146
writeLPGLPK, 147
writeMIPGLPK, 148
writeMPSGLPK, 149
writeProbGLPK, 150
writeSolGLPK, 151
∗ **package**
glpkAPI-package, 5

addColsGLPK, 6
addRowsGLPK, 7
advBasisGLPK, 8

bfExistsGLPK, 9
bfUpdatedGLPK, 10
BINARIZE *(*glpkConstants*)*, 77
BR_TECH *(*glpkConstants*)*, 77
BT_TECH *(*glpkConstants*)*, 77

CB_FUNC *(*glpkConstants*)*, 77
CB_SIZE *(*glpkConstants*)*, 77
checkDupGLPK, 11
CLQ_CUTS *(*glpkConstants*)*, 77

constantsGLPK *(glpkConstants)*, 77
copyProbGLPK, 12
COV_CUTS *(glpkConstants)*, 77
cpxBasisGLPK, 13
createIndexGLPK, 13, *19, 20*

delColsGLPK, 14
deleteIndexGLPK, 15
delProbGLPK, 16
delRowsGLPK, 16

EPS_TOL *(glpkConstants)*, 77
eraseProbGLPK, 17

factorizeGLPK, 18
findColGLPK, 19
findRowGLPK, 20
FP_HEUR *(glpkConstants)*, 77

getBfcpGLPK, 21
getBheadGLPK, 22
getCbindGLPK, 23
getColDualGLPK, 24, *31*
getColDualIptGLPK, 25, *31*
getColKindGLPK, 26, *32*
getColLowBndGLPK, 27, *33*
getColNameGLPK, 28
getColPrimGLPK, 29, *34*
getColPrimIptGLPK, 30
getColsDualGLPK, 31
getColsDualIptGLPK, 31
getColsKindGLPK, 32
getColsLowBndsGLPK, 33
getColsPrimGLPK, 34
getColsPrimIptGLPK, 34
getColsStatGLPK, 35
getColStatGLPK, *35*, 36
getColsUppBndsGLPK, 37
getColTypeGLPK, 38
getColUppBndGLPK, *37*, 39
getDualStatGLPK, 40
getInteriorParmGLPK, 41
getMatColGLPK, 42
getMatRowGLPK, 43
getMIPParmGLPK, 44
getNumBinGLPK, 45
getNumColsGLPK, 45
getNumIntGLPK, 46
getNumNnzGLPK, 47
getNumRowsGLPK, 48
getObjCoefGLPK, 48, *49*
getObjCoefsGLPK, 49
getObjDirGLPK, 50
getObjNameGLPK, 51
getObjValGLPK, 52
getObjValIptGLPK, 52
getPrimStatGLPK, 53
getProbNameGLPK, 54
getRbindGLPK, 55
getRiiGLPK, 56
getRowDualGLPK, 57, *63*
getRowDualIptGLPK, 58, *63*
getRowLowBndGLPK, 59, *64*
getRowNameGLPK, 60
getRowPrimGLPK, 61, *65*
getRowPrimIptGLPK, 62, *66*
getRowsDualGLPK, 63
getRowsDualIptGLPK, 63
getRowsLowBndsGLPK, 64
getRowsPrimGLPK, 65
getRowsPrimIptGLPK, 66
getRowsStatGLPK, 66
getRowStatGLPK, *66*, 67
getRowsTypesGLPK, 68
getRowsUppBndsGLPK, 69
getRowTypeGLPK, *68*, 70
getRowUppBndGLPK, *69*, 71
getSimplexParmGLPK, 72
getSjjGLPK, 73
getSolStatGLPK, 74
getSolStatIptGLPK, 75
getUnbndRayGLPK, 76
glp_add_cols *(addColsGLPK)*, 6
glp_add_rows *(addRowsGLPK)*, 7
glp_adv_basis *(advBasisGLPK)*, 8
GLP_BF_BG *(glpkConstants)*, 77
GLP_BF_BTF *(glpkConstants)*, 77
glp_bf_exists *(bfExistsGLPK)*, 9
GLP_BF_FT *(glpkConstants)*, 77
GLP_BF_GR *(glpkConstants)*, 77
GLP_BF_LUF *(glpkConstants)*, 77
glp_bf_updated *(bfUpdatedGLPK)*, 10
GLP_BR_DTH *(glpkConstants)*, 77
GLP_BR_FFV *(glpkConstants)*, 77
GLP_BR_LFV *(glpkConstants)*, 77
GLP_BR_MFV *(glpkConstants)*, 77
GLP_BR_PCH *(glpkConstants)*, 77

GLP_BS (glpkConstants), 77
GLP_BT_BFS (glpkConstants), 77
GLP_BT_BLB (glpkConstants), 77
GLP_BT_BPH (glpkConstants), 77
GLP_BT_DFS (glpkConstants), 77
GLP_BV (glpkConstants), 77
glp_check_dup (checkDupGLPK), 11
glp_copy_prob (copyProbGLPK), 12
glp_cpx_basis (cpxBasisGLPK), 13
glp_create_index (createIndexGLPK), 13
glp_create_prob (initProbGLPK), 84
GLP_CV (glpkConstants), 77
GLP_DB (glpkConstants), 77
glp_del_cols (delColsGLPK), 14
glp_del_rows (delRowsGLPK), 16
glp_delete_index (deleteIndexGLPK), 15
glp_delete_prob (delProbGLPK), 16
GLP_DN_BRNCH (glpkConstants), 77
GLP_DUAL (glpkConstants), 77
GLP_DUALP (glpkConstants), 77
GLP_EBADB (glpkConstants), 77
GLP_EBOUND (glpkConstants), 77
GLP_ECOND (glpkConstants), 77
GLP_EDATA (glpkConstants), 77
GLP_EFAIL (glpkConstants), 77
GLP_EINSTAB (glpkConstants), 77
GLP_EITLIM (glpkConstants), 77
GLP_EMIPGAP (glpkConstants), 77
GLP_ENOCVG (glpkConstants), 77
GLP_ENODFS (glpkConstants), 77
GLP_ENOFEAS (glpkConstants), 77
GLP_ENOPFS (glpkConstants), 77
GLP_EOBJLL (glpkConstants), 77
GLP_EOBJUL (glpkConstants), 77
GLP_ERANGE (glpkConstants), 77
glp_erase_prob (eraseProbGLPK), 17
GLP_EROOT (glpkConstants), 77
GLP_ESING (glpkConstants), 77
GLP_ESTOP (glpkConstants), 77
GLP_ETMLIM (glpkConstants), 77
glp_exact (solveSimplexExactGLPK), 139
glp_factorize (factorizeGLPK), 18
GLP_FEAS (glpkConstants), 77
glp_find_col (findColGLPK), 19
glp_find_row (findRowGLPK), 20
GLP_FR (glpkConstants), 77
GLP_FX (glpkConstants), 77
glp_get_bfcp (getBfcpGLPK), 21
glp_get_bhead (getBheadGLPK), 22
glp_get_col_bind (getCbindGLPK), 23
glp_get_col_dual (getColDualGLPK), 24
glp_get_col_kind (getColKindGLPK), 26
glp_get_col_lb (getColLowBndGLPK), 27
glp_get_col_name (getColNameGLPK), 28
glp_get_col_prim (getColPrimGLPK), 29
glp_get_col_stat (getColStatGLPK), 36
glp_get_col_type (getColTypeGLPK), 38
glp_get_col_ub (getColUppBndGLPK), 39
glp_get_dual_stat (getDualStatGLPK), 40
glp_get_mat_col (getMatColGLPK), 42
glp_get_mat_row (getMatRowGLPK), 43
glp_get_num_bin (getNumBinGLPK), 45
glp_get_num_cols (getNumColsGLPK), 45
glp_get_num_int (getNumIntGLPK), 46
glp_get_num_nz (getNumNnzGLPK), 47
glp_get_num_rows (getNumRowsGLPK), 48
glp_get_obj_coef (getObjCoefGLPK), 48
glp_get_obj_dir (getObjDirGLPK), 50
glp_get_obj_name (getObjNameGLPK), 51
glp_get_obj_val (getObjValGLPK), 52
glp_get_prim_stat (getPrimStatGLPK), 53
glp_get_prob_name (getProbNameGLPK), 54
glp_get_rii (getRiiGLPK), 56
glp_get_row_bind (getRbindGLPK), 55
glp_get_row_dual (getRowDualGLPK), 57
glp_get_row_lb (getRowLowBndGLPK), 59
glp_get_row_name (getRowNameGLPK), 60
glp_get_row_prim (getRowPrimGLPK), 61
glp_get_row_stat (getRowStatGLPK), 67
glp_get_row_type (getRowTypeGLPK), 70
glp_get_row_ub (getRowUppBndGLPK), 71
glp_get_sjj (getSjjGLPK), 73
glp_get_status (getSolStatGLPK), 74
glp_get_unbnd_ray (getUnbndRayGLPK), 76
GLP_IBINGO (glpkConstants), 77
GLP_IBRANCH (glpkConstants), 77
GLP_ICUTGEN (glpkConstants), 77
GLP_IHEUR (glpkConstants), 77
GLP_INFEAS (glpkConstants), 77
glp_init_iocp (setDefaultMIPParmGLPK), 118
glp_init_iptcp (setDefaultIptParmGLPK), 118
glp_interior (solveInteriorGLPK), 137
glp_intopt (solveMIPGLPK), 138
GLP_IPREPRO (glpkConstants), 77

GLP_IPT (glpkConstants), 77
glp_ipt_col_dual (getColDualIptGLPK), 25
glp_ipt_col_prim (getColPrimIptGLPK), 30
glp_ipt_obj_val (getObjValIptGLPK), 52
glp_ipt_row_dual (getRowDualIptGLPK), 58
glp_ipt_row_prim (getRowPrimIptGLPK), 62
glp_ipt_status (getSolStatIptGLPK), 75
GLP_IROWGEN (glpkConstants), 77
GLP_ISELECT (glpkConstants), 77
GLP_IV (glpkConstants), 77
GLP_KKT_CS (glpkConstants), 77
GLP_KKT_DB (glpkConstants), 77
GLP_KKT_DE (glpkConstants), 77
GLP_KKT_PB (glpkConstants), 77
GLP_KKT_PE (glpkConstants), 77
GLP_LO (glpkConstants), 77
glp_load_matrix (loadMatrixGLPK), 85
GLP_MAX (glpkConstants), 77
GLP_MIN (glpkConstants), 77
GLP_MIP (glpkConstants), 77
glp_mip_col_val (mipColValGLPK), 87
glp_mip_obj_val (mipObjValGLPK), 88
glp_mip_row_val (mipRowValGLPK), 89
glp_mip_status (mipStatusGLPK), 90
glp_mpl_alloc_wksp (mplAllocWkspGLPK), 91
glp_mpl_build_prob (mplBuildProbGLPK), 92
glp_mpl_free_wksp (mplFreeWkspGLPK), 93
glp_mpl_generate (mplGenerateGLPK), 94
glp_mpl_postsolve (mplPostsolveGLPK), 95
glp_mpl_read_data (mplReadDataGLPK), 96
glp_mpl_read_model (mplReadModelGLPK), 97
GLP_MPS_DECK (glpkConstants), 77
GLP_MPS_FILE (glpkConstants), 77
GLP_MSG_ALL (glpkConstants), 77
GLP_MSG_DBG (glpkConstants), 77
GLP_MSG_ERR (glpkConstants), 77
GLP_MSG_OFF (glpkConstants), 77
GLP_MSG_ON (glpkConstants), 77
GLP_NF (glpkConstants), 77
GLP_NL (glpkConstants), 77
GLP_NO_BRNCH (glpkConstants), 77
GLP_NOFEAS (glpkConstants), 77
GLP_NS (glpkConstants), 77
GLP_NU (glpkConstants), 77
GLP_OFF (glpkConstants), 77
GLP_ON (glpkConstants), 77
GLP_OPT (glpkConstants), 77
GLP_ORD_AMD (glpkConstants), 77
GLP_ORD_NONE (glpkConstants), 77
GLP_ORD_QMD (glpkConstants), 77
GLP_ORD_SYMAMD (glpkConstants), 77
GLP_PP_ALL (glpkConstants), 77
GLP_PP_NONE (glpkConstants), 77
GLP_PP_ROOT (glpkConstants), 77
GLP_PRIMAL (glpkConstants), 77
glp_print_ipt (printIptGLPK), 98
glp_print_mip (printMIPGLPK), 99
glp_print_ranges (printRangesGLPK), 100
glp_print_sol (printSolGLPK), 101
GLP_PT_PSE (glpkConstants), 77
GLP_PT_STD (glpkConstants), 77
glp_read_ipt (readIptGLPK), 102
glp_read_lp (readLPGLPK), 103
glp_read_mip (readMIPGLPK), 104
glp_read_mps (readMPSGLPK), 105
glp_read_prob (readProbGLPK), 106
glp_read_sol (readSolGLPK), 107
GLP_RF_CLQ (glpkConstants), 77
GLP_RF_COV (glpkConstants), 77
GLP_RF_CUT (glpkConstants), 77
GLP_RF_GMI (glpkConstants), 77
GLP_RF_LAZY (glpkConstants), 77
GLP_RF_MIR (glpkConstants), 77
GLP_RF_REG (glpkConstants), 77
GLP_RT_HAR (glpkConstants), 77
GLP_RT_STD (glpkConstants), 77
glp_scale_prob (scaleProbGLPK), 108
glp_set_bfcp (setBfcpGLPK), 109
glp_set_col_bnds (setColBndGLPK), 110
glp_set_col_kind (setColKindGLPK), 111
glp_set_col_name (setColNameGLPK), 112
glp_set_col_stat (setColStatGLPK), 117
glp_set_mat_col (setMatColGLPK), 121
glp_set_mat_row (setMatRowGLPK), 122
glp_set_obj_coef (setObjCoefGLPK), 124
glp_set_obj_dir (setObjDirGLPK), 126
glp_set_obj_name (setObjNameGLPK), 127
glp_set_prob_name (setProbNameGLPK), 128
glp_set_rii (setRiiGLPK), 129
glp_set_row_bnds (setRowBndGLPK), 130
glp_set_row_name (setRowNameGLPK), 131
glp_set_row_stat (setRowStatGLPK), 134
glp_set_sjj (setSjjGLPK), 136

GLP_SF_2N (glpkConstants), 77
GLP_SF_AUTO (glpkConstants), 77
GLP_SF_EQ (glpkConstants), 77
GLP_SF_GM (glpkConstants), 77
GLP_SF_SKIP (glpkConstants), 77
glp_simplex (solveSimplexGLPK), 140
GLP_SOL (glpkConstants), 77
glp_sort_matrix (sortMatrixGLPK), 141
glp_std_basis (stdBasisGLPK), 142
glp_term_out (termOutGLPK), 143
GLP_UNBND (glpkConstants), 77
GLP_UNDEF (glpkConstants), 77
glp_unscale_prob (unscaleProbGLPK), 144
GLP_UP (glpkConstants), 77
GLP_UP_BRNCH (glpkConstants), 77
glp_version (versionGLPK), 144
glp_warm_up (warmUpGLPK), 145
glp_write_ipt (writeIptGLPK), 146
glp_write_lp (writeLPGLPK), 147
glp_write_mip (writeMIPGLPK), 148
glp_write_mps (writeMPSGLPK), 149
glp_write_prob (writeProbGLPK), 150
glp_write_sol (writeSolGLPK), 151
glpk_Constants (glpkConstants), 77
glpkAPI (glpkAPI-package), 5
glpkAPI-package, 5
glpkConstants, *12*, *19*, *21*, *36*, *38*, *40*, *41*, *44*, *51*, *54*, *68–70*, *72*, *74*, *75*, 77, *95*, *105*, *108–121*, *123*, *126*, *130–135*, *137–140*, *142*, *143*, *149*
glpkPointer (glpkPtr-class), 83
glpkPointer,glpkPtr-method (glpkPtr-class), 83
glpkPtr, *7–10*, *12–40*, *42*, *43*, *45–71*, *73–76*, *85–107*, *109–117*, *121*, *122*, *124–134*, *136–142*, *144–151*
glpkPtr (glpkPtr-class), 83
glpkPtr-class, 83
glpkPtrType (glpkPtr-class), 83
glpkPtrType,glpkPtr-method (glpkPtr-class), 83
glpkPtrType<- (glpkPtr-class), 83
glpkPtrType<-,glpkPtr-method (glpkPtr-class), 83
GMI_CUTS (glpkConstants), 77

initProbGLPK, *7–10*, *12–40*, *42*, *43*, *45–71*, *73–76*, 84, *84–90*, *98–107*, *109–117*, *121*, *122*, *124–134*, *136–142*, *144–151*
isGLPKpointer (glpkPtr-class), 83
isGLPKpointer,glpkPtr-method (glpkPtr-class), 83
isNULLpointerGLPK (glpkPtr-class), 83
isNULLpointerGLPK,glpkPtr-method (glpkPtr-class), 83
isTRWKSpointer (glpkPtr-class), 83
isTRWKSpointer,glpkPtr-method (glpkPtr-class), 83
IT_LIM (glpkConstants), 77

loadMatrixGLPK, 85
LU_SIZE (glpkConstants), 77

MAX_GRO (glpkConstants), 77
METH (glpkConstants), 77
MIP_GAP (glpkConstants), 77
mipColsValGLPK, 86
mipColValGLPK, *86*, 87
mipObjValGLPK, 88
mipRowsValGLPK, 88
mipRowValGLPK, *88*, 89
mipStatusGLPK, 90
MIR_CUTS (glpkConstants), 77
mplAllocWkspGLPK, *84*, 91, *92–97*
mplBuildProbGLPK, 92, *93–97*
mplFreeWkspGLPK, *92*, 93, *94–97*
mplGenerateGLPK, *92*, *93*, 94, *95–97*
mplPostsolveGLPK, *92–94*, 95, *96*, *97*
mplReadDataGLPK, *92–95*, 96, *97*
mplReadModelGLPK, *92–96*, 97
MSG_LEV (glpkConstants), 77

NFS_MAX (glpkConstants), 77
NRS_MAX (glpkConstants), 77

OBJ_LL (glpkConstants), 77
OBJ_UL (glpkConstants), 77
ORD_ALG (glpkConstants), 77
OUT_DLY (glpkConstants), 77
OUT_FRQ (glpkConstants), 77

PIV_LIM (glpkConstants), 77
PIV_TOL (glpkConstants), 77
PP_TECH (glpkConstants), 77
PRESOLVE (glpkConstants), 77
PRICING (glpkConstants), 77

printIptGLPK, 98, *99*, *101*, *102*, *104*, *107*, *146*, *148*, *151*
printMIPGLPK, *98*, 99, *101*, *102*, *104*, *107*, *146*, *148*, *151*
printRangesGLPK, 100
printSolGLPK, *98*, *99*, 101, *102*, *104*, *107*, *146*, *148*, *151*

R_TEST *(glpkConstants)*, 77
readIptGLPK, *98*, *99*, *101*, 102, *104*, *107*, *146*, *148*, *151*
readLPGLPK, 103, *105*, *106*, *147*, *149*, *150*
readMIPGLPK, *98*, *99*, *101*, *102*, 104, *107*, *146*, *148*, *151*
readMPSGLPK, *103*, 105, *106*, *147*, *149*, *150*
readProbGLPK, *103*, *105*, 106, *147*, *149*, *150*
readSolGLPK, *98*, *99*, *101*, *102*, *104*, 107, *146*, *148*, *151*
return_codeGLPK, *83*, 108, *137–140*
RS_SIZE *(glpkConstants)*, 77

scaleProbGLPK, 108
setBfcpGLPK, 109
setColBndGLPK, 110, *113*, *125*
setColKindGLPK, 111, *115*
setColNameGLPK, 112, *116*
setColsBndsGLPK, 113, *114*
setColsBndsObjCoefsGLPK, 114
setColsKindGLPK, 115
setColsNamesGLPK, 116
setColStatGLPK, 117
setDefaultIptParmGLPK, 118
setDefaultMIPParmGLPK, 118
setDefaultSmpParmGLPK, 119
setInteriorParmGLPK, 120
setMatColGLPK, 121
setMatRowGLPK, 122
setMIPParmGLPK, 123
setObjCoefGLPK, 124
setObjCoefsGLPK, *114*, 125
setObjDirGLPK, 126
setObjNameGLPK, 127
setProbNameGLPK, 128
setRhsZeroGLPK, 129
setRiiGLPK, 129
setRowBndGLPK, 130, *132*
setRowNameGLPK, 131, *133*
setRowsBndsGLPK, *129*, 132
setRowsNamesGLPK, 133
setRowStatGLPK, 134
setSimplexParmGLPK, 135
setSjjGLPK, 136
solveInteriorGLPK, 137
solveMIPGLPK, 138
solveSimplexExactGLPK, 139
solveSimplexGLPK, 140
sortMatrixGLPK, 141
status_codeGLPK, *83*, 141
stdBasisGLPK, 142
SUHL *(glpkConstants)*, 77

termOutGLPK, 143
TM_LIM *(glpkConstants)*, 77
TOL_BND *(glpkConstants)*, 77
TOL_DJ *(glpkConstants)*, 77
TOL_INT *(glpkConstants)*, 77
TOL_OBJ *(glpkConstants)*, 77
TOL_PIV *(glpkConstants)*, 77
TYPE *(glpkConstants)*, 77

unscaleProbGLPK, 144
UPD_TOL *(glpkConstants)*, 77

versionGLPK, 144

warmUpGLPK, 145
writeIptGLPK, *98*, *99*, *101*, *102*, *104*, *107*, 146, *148*, *151*
writeLPGLPK, *103*, *105*, *106*, 147, *149*, *150*
writeMIPGLPK, *98*, *99*, *101*, *102*, *104*, *107*, *146*, 148, *151*
writeMPSGLPK, *103*, *105*, *106*, *147*, 149, *150*
writeProbGLPK, *103*, *105*, *106*, *147*, *149*, 150
writeSolGLPK, *98*, *99*, *101*, *102*, *104*, *107*, *146*, *148*, 151